



NETOP®

RemoteControl

Secure Remote Management and Support

User Guide

Thursday, May 27, 2021

Table of Contents

Foreword	0
Part I Overview	5
1 Remote Control Modules	5
2 Security	6
3 Communication profiles	6
Part II Managing Hosts	8
1 Start and end a remote control session	8
2 Use Netop phonebook to manage connections	10
Edit phonebook records	11
Protect your phonebook record files with a password	11
Organize your phonebook	12
Export and import phonebook data	12
Add a phonebook reference	14
Use Remote Desktop from the Netop phonebook	14
3 Keyboard, mouse and display during remote control	15
4 Generate a Host inventory	15
Process Host computer inventory information	16
5 Monitor Hosts	17
6 Execute system control commands on a Host computer	18
7 Perform Remote Management tasks	19
Management pane	20
Disk Drives	20
Event Viewer	21
Task Manager	22
Registry	22
Services	22
Shared Folders	24
Inventory	25
Command Console	25
System Control	25
Local Users and Groups	26
Integrate third party applications	28
Netop Sessions	30
8 Create and run a script	30
9 Use Intel vPro from Netop Remote Control	33
Log on to the vPro Console	34
vPro Console	36
10 Tunnel	39
Predefine local ports for the tunnel	40
Open tunnel session	41
11 Run a remote program	41
12 Transfer files	42
13 Log events	44
14 Record sessions	45
Play back session recordings	46

15	Use a skin to see the Host button layout	47
16	Multisession Support	48
17	Switching between whitelisted applications	48
18	Multiple monitors support	48
Part III Getting remote support		49
1	Request help	49
2	Notification	49
3	Communicate with Guest users	50
4	End a remote control session from a Host computer	51
Part IV Providing remote support		52
1	Set up Help Request on Guest and Host	52
2	Respond to a help request	55
3	Run a multi Guest session	55
4	Send special keystrokes	56
5	Use clipboard commands	57
6	Communicate with Host users	58
7	Send or receive print jobs	60
	Redirect a print job	61
8	Share your screen	61
9	Netop Screen Video	62
10	Netop Marker Utility	64
Part V Dialog box help		65
1	Guest dialog boxes	65
	Advanced audio settings	65
	Advanced Help Service	65
	Advanced inventory option	67
	Advanced TCP/IP Configuration	68
	Advanced Video	69
	Communication Profile Edit	70
	Communication Profile Setup	78
	Connect to Host	79
	Connection Properties	80
	Inventory	90
	Name Not Found	91
	Custom Inventory Items	91
	Global Settings	92
	IP Broadcast List	94
	Log Setup	95
	Available Netop log event codes and arguments - Guest.....	100
	Available Netop log event codes and arguments - Host.....	102
	Netop File Manager Options	108
	Modem	112
	Modem Configuration	112
	Novell Network Numbers	113
	Program Options	113
	Run	129
	Script	130
	Send Message	132

2 Host dialog boxes	133
Advanced Help Request Options	133
Allowed ISDN Numbers	133
Directory Service	134
Guest Access Security	136
Guest Profile	147
Help Providers	149
Help Request	149
Maintenance Password	150
Program Options	151
Select Directory Services Users or Groups	162

Index**163**

1 Overview

1.1 Remote Control Modules

Netop Remote Control is comprised out of the following modules:

- **Netop Guest:** Enables the computer user to remote control and interact with another computer that runs a Netop **Host** or an extended **Host**.
- **Netop Host:** Enables the computer to be remote controlled and interacted with from a computer that runs a **Netop Guest**.
- **Netop WebConnect / 3:** A secure web-based service consisting of a **Connection Manager** that serves as a meeting hub for the **Netop Guests** and **Hosts**, and at least one **Connection Server** that routes the traffic between the **Guests** and **Hosts**. The **Connection Server** is an extended **Host**. This is available as a hosted service or as an on-premise application. **WebConnect 3.0** has an improved security.
- **Netop Portal:** A management console allowing the users to manage authentication and authorization, view connected devices, do remote sessions and create packages for device enrollment.
- **Netop Browser Based Support Console:** A browser based interface for the **Guest**, that allows the supporters to remote control devices, no installation required.
- **Netop Security Server:** An extended **Host** that uses a central database to manage **Guest** authentication and authorization across the network. It also provides centralized logging capabilities and extended authentication methods including RSA.
- **Netop Gateway:** An extended **Host** that can route Netop traffic between different communication devices. Netop Gateway can receive Netop communication that uses one communication device and send it using another communication device. This ability enables **Netop Gateway** to provide communication between Netop modules that use mutually incompatible communication devices, typically to connect Netop modules inside a network or terminal server environment with Netop modules outside a network or terminal server environment.
- **Netop Name Server:** An extended **Host** that can connect Netop modules across segmented networks. **Netop Name Server** resolves Netop names into IP addresses, that can be used for connecting across any TCP/IP network including the Internet.

See also

The [Netop Remote Control Administrator's Guide](#) for more information about the Security Server, the Gateway and the Name Server.

The [Netop WebConnect Installation Guide](#) for more information about the WebConnect Connection Server.

1.2 Security

You can prevent changes to the installed Netop Remote Control modules by using a maintenance password. You also can hide the **Host** module from the end user via the stealth mode feature.

The **Guest Access Security** functions of the **Host** can protect against unauthorized access and limit the actions available to the **Guest**:

Upon connection to the **Host**, the **Guest** can be authenticated against their Windows login credentials.

Security roles can be defined on the **Host** which dictate what remote control actions the authenticated **Guest** can perform.

The policy functions can determine how the **Host** behaves before, during and after the remote control session, including notification, confirm access and confirm access via email, and illegal connection attempts.

The communication between the Netop modules can be encrypted using different methods that depend on the environment.

Audit trails including all the remote control events and physical session recordings can be centrally maintained.

All the Netop Remote Control modules can log Netop events locally and centrally in a Netop log.

You can protect the **Guest** and **Host** setup with a maintenance password.

See also

[Guest Access Security](#)

[Program Options](#) (Encryption tab and Smart Card tab)

[Administrator's Guide](#)

1.3 Communication profiles

To make the Netop modules to able to communicate with each other, it is necessary that you define a communication profile. A communication profile is a specific configuration of a communication device.

A communication device is a Netop adaptation of a generally available communication protocol or a Netop proprietary communication protocol.

A newly installed Netop module includes the default communication profiles.

NOTE: Communication profiles are stored in the Netop configuration file (`comprof.ndb`). The `comprof.ndb` file is located in the folder `C:\Documents and Settings\<User name>\Application Data\Netop\Netop Remote Control\<Module name>`. Refer to the [Netop KnowledgeBase](#), for more information on how to configure Netop files.

See also


[Communication Profiles](#)

2 Managing Hosts

2.1 Start and end a remote control session

You can connect and start a remote control session in several ways.

Before starting a remote control session, specify a communication profile corresponding to a communication profile (default is TCP/IP = UDP) enabled on the **Host** in the **Communication Profile** section of the **Quick Connect** tab.



To start a remote control session from the **Guest** window, **Quick Connect** tab, proceed as follows:

1. In the **Quick Connect** tab, in the **Host** section, specify a **Host** name or address as required by the selected communication profile.
2. Click on the **Connect** button to connect and start a remote control session. Alternatively, click on a toolbar button or select a command from the **Connection** menu to connect and start a session. Typically, a Netop logon window is displayed prompting you to log on to the **Host**.
3. Type your credentials to log on. When you have logged on to the **Host**, the session starts. Connections are displayed on the **Connections** tab. You can change session type or execute action commands by right-clicking on a **Host** from the **Connections** tab.

Other ways to connect from the **Quick Connect** tab

1. Click on the **Browse** button (Applies only when using profiles that use UDP and WebConnect).
2. Select one or multiple **Hosts** in the **Browse** list (**Netop Network** tab).
3. Click on the **Connect** button. Alternatively, click on a toolbar button or select a command on the **Connection** menu to connect and start a session.

Typically, a Netop logon window is displayed prompting you to log on to the **Host**.

4. Type your credentials to log on. When you have logged on to the **Host**, the session starts.

Alternatively:

1. Click on the **Windows Network** tab at the bottom of the window.
2. In the Windows Network list navigate to and select one or multiple **Hosts**.
3. Click on the **Connect** button. Alternatively, click on a toolbar button or select a command on the **Connection** menu to connect and start a session. Typically, a Netop logon window is displayed prompting you to log on to the **Host**.
4. Type your credentials to log on. When you have logged on to the **Host**, the session starts.

To start a remote control session from other **Guest** window tabs, proceed as follows:

1. In the **Phonebook** tab, **History** tab, or **Help Request** tab, select one or multiple **Hosts**.
2. Click on a toolbar button or select a command on the **Connection** menu to connect and start a session. Typically, a Netop logon window is displayed prompting you to log on to the **Host**.
3. Specify your credentials to log on. When you log in on to the **Host**, the session starts.

Phonebook	Stores Host records that you have created or saved from the Quick Connect tab or History tab.
History	Stores records of previous Host connections.
Help Request	Displays a list of pending Host help requests.

See also

[Save connection information in the phonebook](#)

To end a remote control session, proceed as follows:

In the **Remote Control** window of the **Guest**, click on the **Disconnect** button on the toolbar. Alternatively, click on the **Remote Control** button from the toolbar.

Alternatively:

In the **Guest** window, select the connection from the **Connections** tab.

Click on the **Disconnect** button from the toolbar.

Alternatively, select the **Disconnect** button from the **Connection** menu.

The **Host** user can also end the session by selecting **Disconnect** in the **Session** menu.

2.2 Use Netop phonebook to manage connections

You can save connection information as records in the Netop phonebook for a later use.

The phonebook works much like a personal quick-dial telephone directory with the communication profile needed to connect and passwords.

Passwords are encrypted by a secure algorithm.

Phonebook records are saved as files with the extension `dwc` in the `C:\Documents and Settings\<User name>\Application Data\Netop\Netop Remote Control\Guest\PhBook` folder. The `dwc` files are `*.xml` files. You can view the content of these files in any text editor.

From the **Quick Connect** tab

- You can add connection information to the phonebook by right-clicking on a **Host** record in the pane in lower part of the **Guest** window and selecting **Add to Phonebook** after having browsed for **Hosts**.
- In the displayed dialog box select the phonebook folder in which you want to save the information and click on **OK**.

Alternatively:

1. You can copy connection information to the phonebook by right-clicking on a **Host** record in the pane in the lower part of the **Guest** window and selecting **Copy** after you browsed for the **Hosts**.

2. Click on the **Phonebook** tab, right-click on the folder in the left pane in which you want to save the information, and then select **Paste**.

The **Host** record is displayed in the right pane of the **Phonebook** tab.

From the **History** tab

1. You can add connection information to the phonebook, by right-clicking on a **Host** record in the right pane of the **History** tab and then by selecting **Copy**.

2. Click on the **Phonebook** tab, right-click on the folder in the left pane in which you want to save the information, and select **Paste**.

The **Host** record is displayed in the right pane of the **Phonebook** tab.

Creating phonebook records in the **Phonebook** tab

To create a phonebook record, proceed as follows:

1. Click on the **Phonebook Entry** button from the toolbar.

Alternatively, select **New > Phonebook Entry** in the Edit menu.

The **Connection Properties** dialog box is displayed.

2. Fill in the fields in **Connection Properties** with the necessary information and click on **OK**.

See also

[Connection Properties](#)

[Start and end a remote control session](#)

2.2.1 Edit phonebook records

If you want to edit a phonebook record and change information such as the specified communication profile or the **Host** credentials, you can do that in **Connection Properties**.

To edit a phonebook record, proceed as follows:

1. Select the phonebook record in the right pane of the **Phonebook** tab.

2. Click on the **Connection Properties** button on the toolbar.

Alternatively, select **Connection Properties** from the **Edit** menu. The **Connection Properties** dialog box is displayed.

3. Edit the information and click on **OK**.

You can move phonebook records between the Phonebook root folder and user-created folders using drag-and-drop.

See also

[Connection Properties](#)

2.2.2 Protect your phonebook record files with a password

To protect your phonebook record files (***.dwc**), you can specify a password for each file in **Connection Properties**.

You can specify that the password should be entered every time someone wants to use or edit

the file, or you can specify that the password should be entered only to edit the file.

To specify a password for a phonebook record file, proceed as follows:

1. Select the phonebook record in the right pane of the **Phonebook** tab.
2. Click on the **Connection Properties** button from the toolbar.
3. Click on the **Protect Item** tab.
4. Specify a password and confirm it.

If you want the password only to apply to editing, select the **Connect without password** check box.

5. Click on **OK**.

See also

[Connection Properties](#)

2.2.3 Organize your phonebook

You can create new folders in the phonebook to organize your connection information and make it easier to find the **Host** that you want to connect to.

To create a new folder, proceed as follows:

1. In the **Edit** menu, select **New > Folder**.
2. Enter a name for the folder.
3. Click on **OK**. Alternatively, right-click and create a folder using the shortcut menu.

To create a new subfolder, proceed as follows:

1. In the left pane, select the folder in which you want to create a subfolder.
2. In the **Edit** menu, select **New > Folder**.
3. Enter a name for the folder.
4. Click on **OK**. Alternatively, right-click on the folder in which you want to create a subfolder, and create a subfolder using the shortcut menu.

You can use drag-and-drop to rearrange your folders.

2.2.4 Export and import phonebook data

You can export and import phonebook data in a ***.csv** (comma separated values) file. This is useful for example if you want to copy phonebook data from one computer to another.

You can also populate the phonebook using existing data from another system, for example by

importing data from **Active Directory**.

Scripts can use the phonebook data to call **Hosts**.

To export the phonebook data, proceed as follows:

1. Select a folder in the left pane of the **Phonebook** tab or select one or multiple phonebook records in the right pane.
2. In the **File** menu, select **Export**.
3. In the displayed dialog box, specify the path and name of the ***.csv** file that you want to save the phonebook records to. If you specify only a file name, the export file is saved to the folder in which the Netop **Guest** is installed.
4. Select the **Export Passwords** check box if you want to include passwords for the phonebook records in the ***.csv** file.
5. Click on **OK**.

You cannot export all the **Connection Properties** properties for a phonebook record. This applies to the properties of the **Display** tab, the **Keyboard/Mouse** tab, the **Compression/Encryption** tab, the **Desktop** tab, and the **Record** tab. You can specify these properties when importing.

Csv file syntax

The **.csv** file is a plain text file. For each phonebook record, the file contains a line of values separated by commas according to this syntax:

```
<Folder path>,<Description>,<Phone number>,<Name>,<Comment>,<Communication profile>,<Host logon name>,<Host logon password>,<Host logon domain>,<Gateway logon name>,<Gateway logon password>,<Gateway logon domain>,<Protect item password>,<Wake on LAN MAC address>,<Logon credentials flags>,<Custom application description>,<Custom application command line>
```

Passwords are encrypted as 64-digit hexadecimal checksums with the prefix **ENCRYPTED:**.

To import the phonebook data, proceed as follows:

1. In the **File** menu, select **Import to Phonebook**.
 2. Specify the path to and name of the ***.csv** file that you want to import.
 3. Click on the **Connection Properties** button if you want to specify the **Display** tab properties, **Keyboard/Mouse** tab properties, **Compression/Encryption** tab properties, **Desktop** tab properties, and the **Record** tab properties.
 4. Click on **OK**.
-

2.2.5 Add a phonebook reference

You can add a phonebook reference in the **Guest** phonebook. A phonebook reference links to a folder containing phonebook records (*.dwc files), for instance a phonebook shared by multiple users.

To add a phonebook reference, proceed as follows:

1. Right-click in the left pane of the **Phonebook** tab and select the **Add Phonebook** reference.
2. In the **Add Phonebook Reference** dialog box, specify the folder containing phonebook records that you want to link to.

You can browse for the folder by clicking on the button next to the **Folder** field.

3. Click on **OK**.

A phonebook reference to a folder containing phonebook records is displayed in the left pane of the **Phonebook** tab, and the records are displayed in the right pane.

You can edit the phonebook reference by right-clicking on the reference and selecting the **Edit Phonebook** reference.

2.2.6 Use Remote Desktop from the Netop phonebook

The Netop phonebook provides access to using the Remote Desktop functionality. This means that you can use one tool for all your remote control sessions.

For information about configuration of RDP (Remote Desktop Protocol), please refer to the Microsoft documentation.

To create a Remote Desktop entry in the phonebook, proceed as follows:

1. Right-click in the right pane of the **Phonebook** tab and select **New > Remote Desktop Entry**. The **Remote Desktop Connection** dialog box opens.
2. In the **General** tab, specify the logon settings and a **.rdp** file to be used for the entry.

A **Remote Desktop** entry is created and displayed in the records pane of the **Phonebook** tab together with a pseudo communication profile.

Use the **Remote Desktop** phonebook entry you created to start a remote desktop session.

For information about the use of Remote Desktop, click on the **Help** button in the **Remote Desktop Connection** dialog box.

2.3 Keyboard, mouse and display during remote control

By default the **Guest** and the **Host** share the keyboard and mouse control during remote control. If allowed by the **Guest Access Security** settings on the **Host**, you can block the **Host** user from using the keyboard and mouse. To do so, click on the **Lock Keyboard and Mouse** button from the toolbar in the **Remote Control** window.

You can also blank the **Host** screen, if allowed by the **Guest Access Security** settings on the **Host**, so that what is going on on the **Host** computer cannot be seen by anyone. To do so, click on the **Blank Display** button from the toolbar.

NOTE: While **Blank Display** works with most **Host** computers, the design of some display adapters prevents applying it.

Typically, these two functions are used together, for example if you are carrying out maintenance work on an unattended **Host** computer or working on your office computer from home, and you do not want anyone passing by to see what you are doing or to interfere.

In the **Guest Connection Properties**, in the **Startup** tab, you can specify that the **Host** computer screen should be blanked and the keyboard and mouse should be locked in the **Host** computer from the start when you establish a connection to the **Host**.

See also

[Guest Access Security Connection Properties](#) (Keyboard/Mouse tab)

2.4 Generate a Host inventory

If allowed by the **Guest Access Security** settings on the **Host**, you can generate an inventory of the **Host** computer hardware and software. The inventory are displayed on the **Inventory** tab of the **Guest**.

To define what you want the **Host** inventory summary to contain, proceed as follows:

1. In the **Tools** menu, select **Program Options**.
2. Click on the **Inventory** tab, select/clear selection of elements on the **Summary view** list, and click on **OK**.

To generate a **Host inventory**, proceed as follows:

1. On one of the **Guest** window tabs, select the **Host** computer for which you want to generate

an inventory.

The **Guest** can connect and generate an inventory from the **Quick Connect** tab, the **Phone-book** tab or the **History** tab.

2. Click on the **Get Inventory** button in the toolbar.

Alternatively, select **Get Inventory** in the **Connection** menu.

Alternatively:

If you are already connected to a **Host**, in the **Remote Control** window, click on the **Get Inventory** button on the toolbar.

The inventory as defined in the **Inventory** tab in **Program Options** is displayed in the **Inventory** tab in the **Guest** window.

See also

[Program Options \(Inventory tab\)](#)

[Process Host computer inventory information](#)

2.4.1 Process Host computer inventory information

You can use **Host** computer inventory information to get an overview.

In addition to this you can specify an external program to be executed after an inventory scan has completed. Inventory data is saved in **.xml** files.

You can also specify custom inventory items that you want to include when generating inventories, that is items not included in the list of inventory items in the **Inventory** tab in **Program Options**.

For example you might want to check what version of a certain program is installed on a number of **Host** computers. If you know the registry key for the program version in question, you can specify a custom inventory item for the registry key. You can then generate inventories telling you what version of the program is installed.

To specify a program to run after inventory scan, proceed as follows:

1. In the **Tools** menu, select **Program Options**.
 2. Click on the **Inventory** tab, and click on the **Advanced** button.
 3. In the **Advanced inventory** option dialog box, specify whether you want to run a program after generating an inventory for each **Host** or after generating inventories for all the **Hosts** for which you choose to generate the inventories.
-

4. In the **File** name field, specify the program file name. Click on the **Browse** button to find the program.

5. Then click on **OK**.

When you generate **Host** inventories, the specified program runs automatically afterwards as specified.

Specify custom inventory items

You can retrieve additional information during the inventory scan, such as environment variables, registry keys, file information etc.

1. In the **Tools** menu, select **Program Options**.

2. Click on the **Inventory** tab, and click on the **Advanced** button.

3. In the **Advanced inventory** option dialog box, click on the **Add** button.

4. In the **Custom Inventory** Items dialog box, enter a name for the custom inventory item.

Select item type on the Item **Type** list, for example Registry key, and fill in all fields for the selected item type as necessary.

Then click on **OK**.

The custom inventory item you created is displayed in the **Custom Inventory Items** pane in the Advanced inventory option dialog box. From here you can edit or delete it.

NOTE: The pane contents are stored in the Netop configuration file **InvCuItm.xml**, which is typically located here: `C:\Documents and Settings\\Application Data\Netop\Netop Remote Control\Guest`.

2.5 Monitor Hosts

If the **Guest Access Security** settings on the **Hosts** allow remote control, the **Guest** can sequentially monitor the computer screen images of multiple **Hosts** and toggle between monitor mode and remote control mode.

During monitoring most **Guest** toolbar buttons are disabled, the **Guest** has no keyboard and mouse control on the **Host** computer.

If you discover during monitoring that you need to do something on the **Host** being monitored, switch to remote control mode using the **Monitor/Remote Control** toggle button in the monitor toolbox. Not all remote control functionality is available.

Each **Host** is monitored for a specified number of seconds. Specify the monitor interval in **Tools > Program Options > Monitor**.

In the **Host**, monitoring appears as multiple short remote control sessions.

To start monitoring **Hosts**, proceed as follows:









1. Select **Hosts** from the **Quick Connect** tab, the **Phonebook** tab or the **History** tab.
2. Click on the **Monitor** button on the toolbar to start connecting to the first selected **Host**.

Alternatively, select **Monitor** in the **Connection** menu.

3. If prompted by the **Host**, enter the logon information to log on to the **Host**.

You see the first **Host** computer.

4. The monitor toolbox is displayed. Use the tools to control the monitoring.

Button	Description
	End monitoring.
	Continue countdown after Hold.
	Hold countdown.
	Monitor the previous Host .
	Monitor the next Host .
	Switch between monitor and remote control mode. The button displays a remote control icon in monitor mode and a monitor icon in remote control mode.
	Switch between window and full screen. The button displays a window to full screen icon in window mode and a full screen to window icon in full screen mode.
	Display a list of monitored Hosts . Use it to select a specific Host to monitor.

NOTE: The **Guest** cannot monitor a **Host** computer with which it runs a remote control session.

2.6 Execute system control commands on a Host computer

If allowed by the **Guest Access Security** settings on the **Host**, the **Guest** can execute system control commands on **Host** computers.

To execute a system control command on a **Host** computer, proceed as follows:

1. In one of the **Guest** window tabs, select the **Host** computer that you want to connect to and execute a system control command on.

The **Guest** can connect and execute a system control command from the **Quick Connect** tab, the **Phonebook** tab or the **History** tab in the **Guest** window.

2. Click on the **Execute Command** button on the toolbar.

Alternatively, select the **Execute Command** from the **Connection** menu.

or

When already connected, in the Remote Control window, click on the **Execute Command** button in the toolbar.

Execute Command displays a menu from which you can select the following commands:

Command	Note
Log Off	
Restart	
Shut Down	
Lock Workstation	You can lock only Host computers running on Windows NT and later (2000, XP, 2003, 2008, Vista, and 7) operating systems.
Wake on LAN	Select Wake on LAN to start selected Host computers whose Wake on LAN MAC Address is specified on the Connect tab in the Connection Properties window. NOTE: You can only use this command for Host computers that support this.

See also

[Guest Access Security](#)

2.7 Perform Remote Management tasks

If allowed by the **Guest Access Security** settings on the **Host**, the **Guest** can use **Remote Management** to manage the **Host**.

For the **Host** computer you can access the Disk drives, Event Viewer, Task Manager, Registry, Services, Shared Folders, Inventory, Command Console, System Control and Local Users and Groups.

The window section called Netop Sessions provides access to a few basic remote control session types, Remote Control, File Transfer, Chat and Audio-Video Chat, which you can use while remote managing the **Host**.

Other third party programs can be installed in their own window section. In the **File** menu, click on the **Third Party Program Integration** button. The first step is to add your own window section, and the next step is to add shortcuts to relevant programs.

To start a remote management session with a **Host**, proceed as follows:

1. In one of the **Guest** window tabs, select the **Host** that you want to connect to and run a remote management session with.

2. Click on the **Remote Management** button on the toolbar to start a remote management session with the selected **Host**.

Alternatively, select **Remote Management** in the **Connection** menu.

The Remote Management window is displayed.

Nothing is displayed on the **Host** computer.

2.7.1 Management pane

When you have started a remote management session with a **Host**, the **Remote Management** window is displayed. The **Remote Management** window contains a pane on the left providing access to available management tools in three or more sections.

Management

The first section provides access to the **Management** tools. The tools are also available from the **Management** menu, which is added to the **Netop Remote Management** menu bar when a remote management session is started.

For details about each tool, refer to the relevant topic below.

Netop Sessions

The second section provides access to Netop Sessions commands. Refer to the Netop Sessions for a brief overview of the command.

Details

The third section is informational only and displays the following information:

- The **Host** ID
- The **Host** computer ID or MAC address
- The **Guest** communication profile
- The encryption type icon and name
- The **Host** computer operating system
- The remote management session duration in this format: HH:MM:SS.

2.7.2 Disk Drives

Click on **Disk Drives** from the **Management** section to display available **Host** computer disk drives and their properties.

Use the **Disk Drives** tool to get an overview of the available disk space on a remote controlled computer.

Viewing options are available from the **Disk Drives** menu and from the shortcut menu that opens when you right-click on the data panel.

2.7.3 Event Viewer

Click on **Event Viewer** in the **Management** section to display Windows event logs of the **Host** computer.

Use the **Event Viewer** tool to:

- View and change log properties.
- View the properties of an event record and copy them to the clipboard.
- Clear logs.
- Save a log on the **Guest** or **Host** computer.
- Open a log saved on the **Guest** or **Host** computer to view it.

NOTE: Only Windows NT and later versions (2000, XP, 2003, 2008, Vista, and 7) record event logs. Consequently, the Event Viewer command is enabled only if the **Host** computer runs on a Windows NT or later operating system.

Like the Windows Event Viewer, the Event Viewer tool includes three categories of information: Application, Security and System.

The File tab can display a saved event log.

The following commands are available from the Event Viewer menu and from the shortcut menu that opens when you right-click on the data panel:

Command	Description
Open	Opens an event log that was previously saved using the Save command. Event log files have the following extension *.evt . NOTE: Opening a saved event log overwrites any previous File tab contents.
Save	Saves an event log as a file in a specified location. The file has the *.evt extension.
Clear	Clears the Application, Security, or System event log from Windows. Before the event log is cleared, you can choose to save the information to a log file. Save the log file saved with *.evt extension.
Refresh	Retrieves new data from the Host computer to refresh the tab display.
Log Properties	Opens the properties window for the Application, Security or System log file. You can view and change log size and filter properties.

Event Properties	Displays properties for the selected event. Use the up and down arrows to scroll through the list of events. Click on the Copy button to copy the record properties to the clipboard.
------------------	---

2.7.4 Task Manager

Click on **Task Manager** in the Management section to display lists of applications and processes that are running on the **Host** computer.

The **Task Manager** tool works like the Windows Task Manager, only on a remote controlled computer. The tool can be used to view and control applications and end processes, and to view the computer load and process threads.

2.7.5 Registry

Click on **Registry** in the **Management** section to open the Windows registry on the **Host** computer.

The **Registry** tool works like the **Windows Registry Editor**, only on a remote controlled computer.

About Windows registry

The Windows registry stores the configuration of the Windows operating system in a structured database. The registry is created when Windows is installed on the computer and is automatically modified when applications are installed and used and when users create or change personal settings. Modify the registry settings with caution as erroneous data entries can make the computer malfunction.

Refer to the **Windows Registry Editor** help for details about entries and how to modify them.

2.7.6 Services

Click on **Services** in the **Management** section to display a list of services that are running on the **Host** computer. Services are programs that can run in the background, that is not displaying on the desktop, to support operating system or application functionalities.

The **Services** tool enables you to start, stop, pause, resume and restart **Host** computer services, to add and remove services and to change the properties of services.

NOTE: Only Windows NT and later (NT, 2000, XP, 2003, 2008, Vista, and 7) can manage services. Consequently, the **Services** command is enabled only if the **Host** computer runs on a

Windows NT or later operating system.

The following commands are available from the Services menu and from the shortcut menu that opens when you right-click the data panel:

Command	Description
Add...	Adds a service on the Host computer. Follow the instructions in the wizard that opens.
Remove	<p>Deletes a service.</p> <p>When a Services record is deleted, the service status and startup type change to "Stopped" and "Disabled". When the application that uses the service is unloaded, the record is removed.</p> <p>NOTE: If you delete a Services record and you remove the service, affects the dependent services. Dependencies are displayed in the Dependencies tab, in the Properties dialog box. Right-click and select Properties from the shortcut menu.</p>
Restart	<p>Stops and starts the service.</p> <p>NOTE: Stopping, pausing or restarting a service can affect dependent services. Dependencies are shown in the Dependencies tab, in the Properties dialog box: Right-click and select Properties from the shortcut menu.</p>
Refresh	Retrieve new information from the Host computer to refresh the displayed information.
Properties	<p>Displays properties for the service on three tab pages.</p> <p>NOTE: Do not change service properties unless you know exactly what you are doing. Keep notes of changes to enable restoring properties if changes cause an unexpected behavior.</p> <p>General tab</p> <p>Use the Startup type field to change the way the service starts.</p> <p>NOTE: If you change the Startup type to "Disabled", a service which started or paused does not change its status. When it is stopped, it can no longer be started.</p> <p>Use the Start, Stop, Pause and Resume buttons to control the service.</p> <p>The Start parameters field is enabled when a service is "Stopped". Specify any parameters like command line options to be used when the service is started.</p> <p>NOTE: Start parameters are unsaved. A backslash (\) is interpreted as an ESCAPE character. Specify two backslashes for each backslash in a parameter.</p>

<p>Log On tab</p> <p>Use the Log on as options to specify how to log on to a service by using a different account.</p> <p>Use Local System account to log on as a local system account that has extensive rights on the Host computer, but no rights on other computers (typically the default selection).</p> <p>Use This account to log on as a specific user and specify the user credentials in the fields.</p> <p>To specify that the selected Host computer service uses the Local Service account, type <code>NT AUTHORITY\LocalService</code>. To specify that it uses the Network Service account, specify <code>NT AUTHORITY\NetworkService</code>. Do not specify a password for these accounts; both of them have built-in passwords.</p> <p>Dependencies tab</p> <p>Displays dependencies and dependents. You cannot change dependencies on this tab.</p>

2.7.7 Shared Folders

Click on **Shared Folders** in the **Management** section to view and manage agent computer shared resources and view and disconnect shared resource sessions and shared file connections.

Shares tab

Special shares, typically with "\$" as the last character in the share name, are created automatically as hidden resources by the operating system for administrative and system use.

Typically, you should not delete or change special shares. If you delete or change special shares, they can be restored when the server service is stopped and restarted or when the computer is restarted.

These special shares may appear on the **Shares** tab:

<Drive letter>\$	Enables Guests to connect to the root directory of a drive.
ADMIN\$	Enables remote administration of a computer. Its path is always the path of the system root directory.
IPC\$	Enables inter program communication by named pipes. <code>IPC\$</code> is used during remote administration of a computer and when viewing a com-

	puter's shared resources and cannot be deleted.
NETLOGON	Required on domain controllers. Removing it causes a loss of functionality on domain client computers.
SYSVOL	Required on domain controllers. Removing it causes a loss of functionality on domain client computers.
PRINT\$	Used during remote administration of printers.
FAX\$	A server folder that is used by clients when sending a fax. It stores temporary fax files and fax cover pages.

2.7.8 Inventory

Click on **Inventory** in the **Management** section for an overview of the **Host** computer inventory of hardware and software.

2.7.9 Command Console

Click on the **Command Console** from the **Management** section to open a command prompt window on the **Host** computer. This corresponds to executing Run on the Windows Start menu and typing **cmd** but have the command prompt window display the **Host** computer, not the **Guest**.

Before the command prompt window opens, you are required to enter credentials (user name, password and domain) that are valid on the **Host** computer.

2.7.10 System Control

Click on the **System Control** in the **Management** section to control the **Host** computer status.

System Control allows you to:

- Lock the computer (Windows NT, 2000, XP, 2003, 2008, Vista and 7 only)
- Log off the user
- Restart the computer
- Shut down the computer

Before any of these actions are performed, you can choose to warn the user by displaying a message, for example:

Computer updates need to be implemented and you are logged off in a

few minutes. Please save your work and close any open program.

Use the **Options** section to specify whether the user is to be warned and to specify the number of seconds between prompting the user and executing the action selected under **Action to Perform**.

Allow user to cancel	Generally, you cannot cancel a system control command. However, selecting this option enables the Abort button on the pop-up message, and the user is allowed to cancel the command.
Close open programs without saving data	Normally data is saved before the selected system control command is executed. Select this option to close any open programs without saving data.

2.7.11 Local Users and Groups

Click on **Local Users and Groups** in the **Management** section to manage users and groups on the **Host** computer.

With **Local Users and Groups**, you can:

- Add new users and groups
- View and edit properties of existing local users and groups
- Set user passwords
- Rename or delete users and groups

Users tab

The **Users** tab contains the list of users of the **Host** computer.

The shortcut menu has these commands:

Command	Description
New User	Select this command to add a new user. In the New User dialog box, specify the appropriate information and select or clear the selection of options related to password and account. Click on Create , and then click on Close .
Set Password	Select this command to change the selected user's password.
Delete	Select this command to delete the selected user. NOTE: When it is necessary for you to remove a user account, it is a good idea

	to disable the account first. When you are certain that when you disable the account did not cause a problem, you can safely delete it. To disable the account, select Account is disabled in the Properties dialog box. A deleted user account cannot be recovered. The built-in Administrator and Guest accounts cannot be deleted.
Rename	Select this command to rename the selected user. Type a new name and press Enter to save. NOTE: Because it retains its security identifier, a renamed user account retains all its other properties, such as its description, password, group memberships, user environment profile, account information, and any assigned permissions and rights. A user name cannot be identical to any other user or group name of the computer being administered. It can contain up to 20 uppercase or lowercase characters, except for the following: " / \ [] : ; = , + * ? < > . A user name cannot consist solely of periods (.) or spaces.
Refresh F5	Select this command to retrieve new data from the Host computer and refresh the tab display.
Properties	Select this command to view and change properties for a user account. When a user has been created with the New User command, the user must be added to a group. This is done on the Member Of tab in the Properties dialog box. NOTE: Adding users to the Administrators group gives them unlimited access rights.

Groups tab

The **Groups** tab contains the list of groups of the **Host** computer.

The shortcut menu has these commands:

Command	Description
New Group	Select this command to add a new group. In the New Group dialog box, type the appropriate information and click on the Add button to add existing users to the group button. Click on Create , and then click on Close . NOTE: A local group name cannot be identical to any other group or user name on the computer being administered. It can contain up to 256 uppercase or lowercase characters, except for the following: " / \ [] : ; = , + * ? < > . A group name cannot consist solely of periods (.) or spaces.
Delete	Select this command to delete the selected group. NOTES: <ul style="list-style-type: none"> The following built-in groups cannot be deleted: Administrators, Backup Operat-

	<p>ors, Power Users, Users, Guests, Replicator.</p> <ul style="list-style-type: none"> • A deleted group cannot be recovered. • Deleting a local group removes only the group; it does not delete the user accounts and global groups that were members of that group. • If you delete a group and then create another group with the same group name, make sure to set new permissions for the new group; it does not inherit the permissions that were granted to the old group.
Rename	<p>Select this command to rename the selected group. Specify a new name and press Enter to save.</p> <p>NOTE: Because it retains its security identifier, a renamed group retains all its other properties, such as its description and members. A group name cannot be identical to any other user or group name of the computer being administered. It can contain up to 20 uppercase or lowercase characters, except for the following: " / \ [] : ; = , + * ? < > . A group name cannot consist solely of periods (.) or spaces.</p>
Refresh F5	<p>Select this command to retrieve new data from the Host computer and refresh the tab display.</p>
Properties	<p>Select this command to add and remove users from the group.</p>

2.7.12 Integrate third party applications

If there are applications that you use frequently in connection with remote management, you can create your own section in the left pane of the Remote Management window and add commands to open any third party application.

The user defined section in the left pane of the **Remote Management** window is added beneath the **Management** section; see illustration and description in the **Management** pane. Within the user defined section, the third party applications can be added beneath user-defined group headings like for example Utilities or Tools.

To add a third party application, proceed as follows:

1. In the **File** menu, click on **Third Party Program Integration**.
2. Click on the **Add Section** button to create the section and give it a name, for example My own section.

Note that the section appears after one or more programs have been added.

3. Select a section and click on the **Add Program** button.
4. In the **Add Program** dialog box, click on the **Browse** button to locate the executable. The Working Folder field is updated automatically.
5. Click on **OK** to add the program and close the dialog box.

Optional parameters

In addition to specifying the name of the executable, optional parameters can also be specified.

Parameter Name	Description
Display Name	Define the program name to be shown in the new section. If this parameter is not set, the name of the executable (for example: excel.exe) is displayed.
Display Name	Define the text to be displayed when the mouse pointer rests on the program name. If this parameter is not set, the name of the executable (for example: excel.exe) is displayed.
Command Line	<p>Define the program parameters to be passed to the program when it is started.</p> <p>The following built-in parameters can be used:</p> <ul style="list-style-type: none"> • %%CN - Host Computer Name • %%CD - Host Computer Domain • %%LU - Host Logged in User • %%LD - Host Logged in Domain • %%IA - Host IP Address • %%MA - Host MAC Address
Working Folder	Select the folder for the program to store its data. If this parameter is not set, the folder where the executable is located is used.
Run As	Select the folder for the program to store its data. If this parameter is not set, the folder where the executable is located is used.

Select how the program window is displayed: **Normal Window**, **Minimized**, **Maximized**, or **Hidden**.

TIP: Any program that is installed on the **Guest** computer and can react to command line executions can be integrated. To view any necessary command line parameters you can open the program properties dialog box: Right-click on the program from the Windows Start menu and then click on **Properties**.

2.7.13 Netop Sessions

The following commands are available in the **Netop Sessions** section:

Command	Description
Remote Control	Start/stop a remote control session with the connected Host .
File Transfer	Start/stop a file transfer session with the connected Host .
Chat	Start/stop a chat session with the connected Host .
Audio-Video Chat	Start/stop an audio-video chat session with the connected Host .

NOTE: **Start Audio-Video Chat** is disabled if the **Guest** and **Host** computers are not both interactive audio enabled or if the **Guest** is engaged in another audio session. The **Guest Access Security** settings on the **Host** can deny a **Guest** starting a session.

2.8 Create and run a script

A script is a user specified command structure that can execute a task, for example an unattended scheduled file transfer.

You create the script in the **Script** dialog box as a tree structure consisting of:

- **Global Settings**, such as overwrite/delete settings, error handling and log file settings etc.
- One or multiple commands, for example a **Wait** command and a **Connect** command to connect to a **Host**.
- One or multiple commands, for example **Copy**, **Delete**, **Synch**, or **Inventory**, which are executed on the **Host** after connection.

The following example describes how to create a script that copies a file from the **Guest** to a **Host** on a specified date and time.

To create this script, proceed as follows:

1. Click on the **Script** tab to display the tab.
2. In the **Edit** menu, select **New > Script** to display the **Script** dialog box.
3. In the **File** name field, enter a name for your script, for example "**Copy document**". If you do not specify a file type extension, the script gets the file type extension ***.dws**.
4. Click on the **Open Script** button and click on **Yes** to start a new script. The **Global Settings** dialog box is displayed.
5. In the **Global Settings** dialog box, specify settings for the script. To close the dialog box, click on **OK**.

6. In the **Comment** field, enter a comment about the script, which is displayed in the **Script** tab in the **Guest** window.

7. Select **Global Settings** in the tree structure in the upper pane of the dialog box, and click on the **Add** button. Select **Wait** on the menu.

8. In the **Wait** dialog box, select **Wait until** in the **Type** field.

Specify a date and time for the copying, and click on **OK** to close the dialog box.

The **Wait** command is added to the script and displayed in the tree structure.

9. Select **Wait** in the tree structure, and click on the **Add** button. Select **Connect** in the menu.

In the **Connect to Host** dialog box, specify how you want to connect to the **Host**, for example using a communication profile.

Select communication profile and specify IP address and logon credentials for the **Host**.

The **Connect** command is added to the script and displayed in the tree structure.

10. Select **Connect** in the tree structure, and click on the **Add** button. Select **Copy** in the menu.

The **Copy** dialog box is displayed.

In the **General** tab, in the **Guest** section, specify the file that you want to copy to the **Host**.

In the **Host** section, specify the location on the **Host** that you want to copy the file to, and change any other settings as necessary.

NOTE: You cannot browse, since the **Guest** is not yet connected to the **Host**.

Click on **OK** to close the dialog box.

11. Click on the **Save Script** button, and click on the **Run** button to enable the script.

12. Click on **Close** to close the dialog box.

You have created a script that copies the `Test.txt` file to one specific **Host** on a specific date and time.

If you want to copy the `Test.txt` file to a number of **Hosts**, the easiest way to specify this in the script is to first edit the script file (Copy the `document.dws` file, located in `\\Application Data\Netop\NetOp Remote Control\Guest\script\`) in Notepad and then edit it further in the **Script** dialog box.

Script file contents

```
;Copy document to Host computer
```

```
;*****
```

```
Script
```

```
SET Copy=G_H
```

```
SET Delta=Yes
SET CrashRecovery=Yes
SET OverwriteExisting=Yes
SET OverwriteSystem=No
SET OverwriteReadOnly=No
SET OverwriteHidden=No
SET OnComError=NextHost
SET OnError=NextFile
SET AtEnd=None
SET UnloadGuest=No
SET LogAppend=No
SET Log=SCRIPT.LOG

WAIT Mode=Until 23:55:00 2009-12-24

Connect /Mode=CommProfile /Profile="LAN (TCP)" /Name="10.45.2.33" /
LoginCredentials=Yes
COPY "C:\Documents and Settings\user1\Desktop\Test.txt" "C:\Docu-
ments and Settings\"
ConnectEnd
ScriptEnd
```

1. Copy the **Connect** command (from `Connect /Mode=` through `ConnectEnd`) for as many Hosts as you want to copy the `Test.txt` file to.
2. Save and close the **Copy** document.dws file.
3. Open the **Copy** document.dws file in the **Script** dialog box again, and for each **Connect** command, edit the IP address and logon credentials in accordance with the individual Hosts that you want to copy the `Test.txt` file to.
4. Save the script.

The script you created automatically copies the `Test.txt` file to a specified range of **Host** computers on the specified date and time.

NOTE: The **Guest** also contains a couple of slightly more advanced example scripts that you can study to see what you can do with Script. See `example1.dws` and `example2.dws` on the **Script** tab. You can open them in Notepad to see the contents.

Once the script has been executed, you can check the script log file (`\\Application Data`

`\Netop\NetOp Remote Control\Guest\`) to see if the script was executed successfully.

See also

[Script](#)

[Global Settings](#)

2.9 Use Intel vPro from Netop Remote Control

The **Netop Remote Control Guest** provides access to **Intel vPro** (sometimes also referred to as **IAMT** - Intel Active Management Technology) functionality which enhances your ability to remote manage enterprise computing facilities.

NOTE: Netop Remote Control **Guest** supports Intel vPro, versions: 2.2 to 1.1. Functionalities introduced after this version are not supported.

The **Guest** can access Intel vPro even when the computer is turned off, as long as the computer is connected to line power and to a network.

NOTE: Due to a limitation in Intel vPro, it is not possible to establish a connection to Intel vPro on the same computer as the one the **Guest** is running on.

The Intel Setup and Configuration Service (SCS) provides tools to centrally set up and configure AMT devices. SCS serves as a server for vPro and is also called a provisioning server.

Depending on which permissions the user has, the following SCS realms are relevant when using the vPro Console that the **Guest** provides access to:

Realm	Comments
General Info	Required
EventLogViewer	If the user has permission to this realm, the Event Management tab is available. The Remove all and Filters and Subscriptions buttons are disabled, so that the user cannot change anything.
Event Management	If the user has permission to this realm, the Event Management tab is enabled and all the buttons are enabled, so that the user can make changes.
Remote Control	If the user has permission to this realm, the Remote Control tab is enabled and the user can execute remote control commands.
Redirection Interface	If the user has permission to this realm, the user can execute serial/IDE redirection commands from the Remote Control tab.

If the user has permissions to neither the **Event Management** tab nor the **Remote Control** tab, an "Authentication failed" message box is displayed. This means that either User or Password is wrong or there are no appropriate permissions for the user in question.

NOTE: Even though computers contain Intel vPro technology, the AMT devices are not be operational until they are enabled (also called provisioning) in the vPro BIOS.

Intel vPro enables you to:

- Remotely access BIOS configuration of the managed computer.
- Remotely boot the managed computer from a floppy or CD-ROM image located on the managing computer.
- Retrieve and view the hardware log file of the managed computer.

2.9.1 Log on to the vPro Console

The **Intel vPro** tab is displayed at the bottom of the **Quick Connect** tab pane following the **Windows Network** tab. When you start the **Guest**, the **Intel vPro** pane is empty.

Right-click on the **Intel vPro** pane to display a context menu containing the following commands:

Command	Description
Scan IP range for Intel vPro enabled computers	<p>Select this command to scan for Intel vPro enabled computers on your network. You can enter one known IP address to scan for or you can enter an IP range to scan.</p> <p>The computers found during the search is listed in the Intel vPro pane by IP address. See picture above.</p> <p>NOTE: You can also use the Guest Inventory tab (Summary - Intel vPro State) to find the Intel vPro enabled computers on your network.</p>
Retrieve the Intel vPro enabled computers from SCS	<p>Select this command or click on the Browse button in the Quick Connect tab to retrieve Intel vPro enabled computers from Intel SCS. Enter the SCS Web Service URL.</p> <p>NOTE: If you do not want to have to enter the SCS Web Service URL every time, go to Tools > Program Options > Intel vPro tab. Select the Connect to SCS check box and enter the SCS Web Service URL in the field below. The address is then saved in the system to avoid entering the address every tome the Retrieve Intel vPro Enabled Computers from SCS command is</p>

selected.

When you have found one or more Intel vPro enabled computers on your network, the above menu is extended with the following commands:

Command	Description
Open Intel vPro Console	Right-click a computer in the list in the Intel vPro pane and select this command to open the vPro Console from which you can manage the selected computer. Use a user name and password to log on.
Open Intel vPro Web Interface	Right-click on a computer from the list in the Intel vPro pane and select this command to go to the Intel vPro Active Management Technology web page (http) from which you can manage the selected computer. Enter a user name and password to log on to the web page.
Open Intel vPro Web Interface (Secure)	As above, but using secured connection (https).
Add to phonebook	Right-click on a computer (IP address) in the list of the Intel vPro pane and select this command to add the address to the phonebook. NOTE: You can also add Intel vPro entries to the phonebook by right-clicking in the right pane on the Phonebook tab.
Delete	Right-click on a computer in the list in the Intel vPro pane and select this command to remove the computer from the list.
Delete All	Right-click on the Intel vPro pane and select this command to remove all computers from the list in the Intel vPro pane.

To log on to the **vPro Console**, proceed as follows:

1. Right-click on a computer on the list in the **Intel vPro** pane and select **Open Intel vPro Console**.
2. In the **Credentials** tab of the displayed Netop vPro Console Logon window, select the authentication method:
 - Digest authentication
 - Kerberos authentication

If you select **Digest authentication**, enter the user name and password.

Select the **Force using secured connection through TLS** check box, if you prefer. Normally, Transport Layer Security (TLS) is automatically detected and used when available, but if you select this check box, the Intel **vPro Console** uses only the secured connection to log on to the AMT device. If the AMT device is not configured to use TLS, you receive an error message and the connection is not established.

If you select **Kerberos authentication**, the tab looks slightly different, and either a current Windows user account or a different user account (user, password, domain) can be used to log on to the AMT device.

In addition to the **Force using secured connection through TLS** check box, you see a **Log on using current Windows account** check box. This check box is selected by default, and as a consequence the **User name**, **Password**, and **Domain** fields are disabled, and the credentials of the current Windows user are used.

NOTE: When using Kerberos authentication the console should be connected to the Host using FQDN name (fully qualified domain name). For example, it is not possible to do the Kerberos authentication when connecting to an AMT device using its IP address.

3. If you select the **Force using secured connection through TLS** check box, a client certificate is required to establish the TLS connection when the AMT device is configured for mutual TLS authentication.

Click on the **Certificate** tab and specify the certificate to be used by first selecting either **Personal Certificate Storage** or **File** in the **Location** list and then selecting the certificate in the Certificate combo box.

4. Click on **Log on** to log on to the **vPro Console**.

When you have logged on, the **vPro Console** window is displayed.

2.9.2 vPro Console

The **vPro Console** window contains a toolbar at the top and two tabs: the **Event Management** tab, on which you can retrieve and view the **Intel vPro Event Log** for the computer being managed, and the **Remote Control** tab, on which you can access the BIOS of the computer, boot from a floppy or CD-ROM image, and manage the power state of the computer remotely.

Event Management tab

The **Event Management** tab displays the **Intel vPro Event Log** for the computer being managed. The events are displayed in the **Intel vPro Event Log** pane with information about severity, time, and entity together with a description. Select an event in the pane to display further de-

tails about the event in the area below the pane.

In the bottom right corner of the **vPro Console** window you see a security indicator, a lock icon. A closed lock indicates that a secured connection is being used, while an open lock indicates that an unsecured connection is being used. In the top right corner you see a network activity indicator that looks like a flower. This icon indicates that the vPro Console is waiting for response from the remote AMT device.

At the top of the **vPro Console** window you find a toolbar with tools that you can apply to the log. In addition to the **Refresh** button, the **Remove All** button, and the **Save to File** button (save events to a *.txt (tab delimited) file or a *.csv file), a **Filters and Subscriptions** button are available.

Remote Control tab

The **Remote Control** tab provides access to the terminal window, which you can use for remote BIOS access and floppy/CD-ROM redirection.

The toolbar for the **Remote Control** tab contains the following buttons:

Button	Description
Remote Control	<p>The menu that opens when you click on the Remote Control button down arrow on the toolbar contains the following menu commands:</p> <ul style="list-style-type: none"> • Normal Reboot • Reboot to BIOS* (If you click the Remote Control button instead of the down arrow, this menu command is selected by default) • Boot from Console Floppy • Boot from Console CD <p>When you select menu commands on the Remote Control menu, you can see the screen of the computer being booted on the Remote Control tab of the vPro Console.</p>
Execute Command	<p>The menu that opens when you click on the Execute Command button down arrow on the toolbar contains the following menu commands:</p> <ul style="list-style-type: none"> • Normal Reboot* (If you click the Execute Command button instead of the down arrow, this menu command is selected by default) • Boot from Console Floppy • Boot from Console CD <p>When you select menu commands on the Execute Command menu,</p>

	<p>the boot command is executed on the remote computer. The screen of the computer being booted on the Remote Control tab of the vPro Console. is unseen.</p>
<p>Power</p>	<p>The menu that opens when you click on the Power button from the toolbar contains the following menu commands, which you can use to manage the power state of the remote computer:</p> <ul style="list-style-type: none"> • Power On • Power Off • Cycle Power Off and On* (default)
<p>Custom command</p>	<p>The menu that opens when you click on the Custom command button down arrow on the toolbar contains the following menu commands, which you can use to customize the menus and menu items to the left of Custom command:</p> <ul style="list-style-type: none"> • Send command - Select this command to open the Send Custom Command dialog box, which allows you to specify a custom command and send it immediately. The custom command is not saved. • Customize - Select this command to open the Customize Remote Control Toolbar dialog box, which allows you to add and specify menus, commands and separators, reorder these elements, and send commands. The changes are saved. You can reset the toolbar again. <p>On the left side in the Customize Remote Control Toolbar dialog box a pane containing the menu structure is displayed. If you select a menu, settings for adjusting the menu are displayed to the right of the pane. You can move the menu up and down in the toolbar, change the appearance of the menu and more.</p> <p>If you select a command in the pane, command options are displayed to the right of the pane.</p> <p>Both dialog boxes contain the same command options. Depending on the command you select, different sets of options are enabled. You can specify command type and parameters, CD/floppy redirection and boot options for the command you select.</p>
<p>IDE Redirection Settings</p>	<p>Clicking on the IDE Redirections Settings button from the toolbar opens the IDE Redirections Settings window where you can select</p>

	<p>settings for Floppy redirection and CD redirection, i.e. the drives and image files that are to be used for Boot from Console Floppy and Boot from Console CD.</p>
<p>Netop vPro Console Settings</p>	<p>Clicking on the Terminal Settings button on the toolbar opens the Netop vPro Console Settings window where you can edit settings for the following:</p> <p>Terminal - Set Font and Emulation.</p> <p>Keyboard - Set Special key mode and Send Esc button code.</p> <p>Warnings - Select the warnings that you want to receive in relation to the Keyboard settings:</p> <ul style="list-style-type: none"> • Warn if the special key mode cannot be detected automatically • Warn when trying to detect keyboard mode without having Hardware Assets Realm permission

2.10 Tunnel

The **Tunnel** function establishes a secure connection between the **Guest** and **Host**. Through the **Tunnel** application ports are redirected from the **Host** to the **Guest**.

This means that the **Guest** can run local applications while interacting with the connected **Host** without having to control the **Host** machine remotely.

The **Tunnel** is ideally suited, but not exclusive to environments where no traditional desktop is available for use with standard remote control (screen, keyboard and mouse control); however support and system administrative tasks still need to be carried out remotely whilst conforming to industry regulatory standards such as PCI-DSS, HIPAA and FIPS.

Such environments can include embedded Linux systems where operating machinery and hardware contains a streamlined version of a Linux operating system, for example, fuel dispensers and retail systems. Enterprises can also take advantage of the Tunnel for managing and supporting their Linux Desktops and Servers using common applications and services such as Shell clients, HTTP and SFTP.

The **Guest's** ability to use the Tunnel along with the associated ports can be governed by the central Netop Security Server solution. This allows organizations to apply granular access privileges. Even when remote systems have a desktop, it may not be required to give Guest users full remote control access on certain machines but limit their ability to use certain application ports through the Netop Tunnel.

2.10.1 Predefine local ports for the tunnel

When using the **Tunnel** capabilities, it is sometimes necessary to configure the local port to a fixed port. This way, when actually tunneling into the machine, the same local port always corresponds to the remote port.

To configure the local ports for the tunnel, proceed as follows:

1. Create the **NetopTunnelPorts.ini** file and define the list of local ports and their corresponding remote ones.

The **.ini** file has the following structure:

```
[default]
key = value
[section]
key = value
```

Where section is the Remote IP, key is the remote port and value is the local predefined port.

2. Place the ***.ini** file in the `C:\windows` folder.

It helps identify either the remote port or the remote IP/remote Hostname/remote port pair and assign it a predefined fixed local port that the **Guest** opens when initiating the tunnel.

NOTES:

- In the **NetopTunnelPorts.ini** file you can define the **Host** by providing either the Host ID or the Host IP Address. When connecting to the **Host**, the proper definitions are used, otherwise the default definition is applied.
- For the TCP/IP communication profile, there might be a cross Host ID - IP Address compatibility. **.ini** file defined with Host ID works if connection is made with Host IP Address or Host ID. Otherwise, the default definition is used.

.ini file sample

```
[default]
80=80
8080=8080
8090=8090
[192.168.201.82]
80=90
8080=91
8090=92
8181=93
[192.168.201.137]
80=94
```


8080=95

8090=96

8181=97

2.10.2 Open tunnel session

The **Guest** can initiate the **Tunnel** session with a **Host** in the same way as any other session:

The **Tunnel** is also available from the context menu on the **Quick Connect** tab, **Phonebook** tab or the **History** tab.

Once the **Guest** is authenticated, the assigned ports are assigned by the **Netop Security Server** and the **Tunnel console** is displayed and confirms which remote ports are available along with the randomly assigned ports that can be used by the **Guest**.

Refer to the separate documentation available on www.netop.com for more details on how to set up and use the secure tunnel.

2.11 Run a remote program

If allowed by the **Guest Access Security** settings on the **Hosts**, the **Netop Guest** can run a program on one or multiple **Host** computers using the **Run Program** function.

To run a program, proceed as follows:

1. In one of the **Guest** window tabs, select the **Host** computer that you want to connect to and run a program on.

The **Guest** can connect and run a program from the **Phonebook** tab, the **Quick Connect** tab, or the **History** tab.

When already connected, the **Guest** can run a program from the **Phonebook** tab, the **Quick Connect** tab, the **Connections** tab or the **History** tab.

2. Click on the **Run Program** button on the toolbar. Alternatively, from the **Connection** menu, select the **Run Program** function.

3. Click on the **Browse** button.

4. In the **Run** dialog box, click on the **Browse** button and select the program that you want to run on the selected **Host** computer.

When the program file is added in the **Local File** name field, the global file name with the absolute path replaced by environment variables is also added in the **Global File Name** field. This is

especially useful if your computers are running different Windows platforms.

Select the **Global File** name option, so that you do not have to consider which operating system version or operating system language the **Host** computer is using.

If the selected program needs to be started using command line switches, use the Command line switches field to type those. This could for example be starting Internet Explorer with a specific address.

Under **Run**, define how the program should start. Select **Normal**, **Maximized** or **Minimized**.

5. Click on **OK** to run the specified program on the selected **Host** computer.

NOTE: It is necessary that the program file is available on the **Host** computer in the location specified in the **Run** dialog box. The program can also be specified on the **Tools > Program Options > Run** tab. If the program is not available on the **Host** computer in the specified location, you can use the **Netop File Manager** to transfer the file to the **Host** before running it. Refer to the [Transfer files](#) section for more information.

2.12 Transfer files

You can use the **Netop File Manager** to transfer files between a **Guest** and a **Host** computer. If allowed by the **Guest Access Security** settings on the **Host**, the **Guest** can start a file transfer session with a **Host** to transfer files between the **Guest** and the **Host** computer. This includes copying, moving, synchronizing, and cloning files.

You can also use the **File Manager** to transfer files locally on the **Guest** computer.

To start a file transfer session, proceed as follows:

1. In one of the **Guest** tabs, select the **Host** to or from which you want to transfer files.

The **Guest** can connect to start a file transfer session from the **Phonebook** tab, the **Quick Connect** tab, or the **History** tab, or in response to a help request from a **Help Request** tab.

When already connected, the **Guest** can start and end a file transfer session from the **Phonebook** tab, the **Quick Connect** tab, the **Connections** tab, or the **History** tab.

2. Click on the **File Transfer** button in the toolbar to open the **File Manager**.

NOTE: If the **Host** allows multiple simultaneous **Guest** connections, multiple **Guests** can run separate file transfer sessions.

Copy files

To copy files from one computer to another, proceed as follows:

1. Select files and/or folders in one of the two **File Manager** panes and click on the **Copy File(s)** button from the toolbar.

Alternatively, select files in one of the two **File Manager** panes and select **Copy File(s)** from the File menu.

2. In the **Copy** dialog box, check the location in the **To** field and change the location if necessary.

Click on the **Options** button to view the **Options** dialog box and specify options for the copy process. Refer to the Netop File Manager Options section for more information.

3. To start the copy process, click on **OK**.

NOTE: You can also use drag-and-drop to copy files from one File Manager pane to the other.

Move files

To move files from one computer to another, proceed as follows:

1. Select the files and/or folders in one of the two **File Manager** panes and click on the **Move File(s)** button from the toolbar.

Alternatively, select files in one of the two **File Manager** panes and select **Move File(s)** from the File menu.

2. In the **Move** dialog box, check the location in the **To** field and change the location if necessary.

Click on the **Options** button to view the **Options** dialog box and specify options for the move process. Refer to the [Netop File Manager Options](#) for more information.

3. Click on **OK** to start the move process.

Synchronize files

To synchronize files between two computers, proceed as follows:

1. Click on the **Synch File(s)** button on the toolbar. Alternatively, select **Synch File(s)** from the **File** menu.

2. In the **Synchronize** dialog box, check the location in the **To** field and change the location if necessary.

Click on the **Options** button to view the **Options** dialog box and specify options for the synchronize process. Refer to the [Netop File Manager Options](#) for more information.

3. Click on **OK** to start the synchronize process.

WARNING! By default, the synchronization process transfers files and folders in both directions,

replacing older files and folders with newer files and folders. In the **Transfer** tab of the **Options** dialog, you can change this into Transfer only if file exists and Transfer only one way for the file transfer process.

Clone Files

To clone files from one computer to another, proceed as follows:

1. Click on the **Clone File(s)** button from the toolbar. Alternatively, select **Clone File(s)** from the **File** menu.

2. In the **Clone** dialog box, check the location in the **To field** and change the location if necessary.

Click on the **Options** button to view the **Options** dialog box and specify options for the clone process. Refer to the [Netop File Manager Options](#) for more information.

3. To start the clone process, click on **OK**.

WARNING! Cloning transfers all the folders and files in the selected pane to the other pane deleting the existing folders and files in it.

TIP: Select all options in the **Confirmation** tab of the **Options** dialog box. Refer to the [Netop File Manager Options](#) for more information. A dialog box is displayed when you are about to delete or overwrite a file, allowing you to choose what you want to do with the file.

Transfer files locally on the Guest computer

To transfer files from one location on the **Guest** computer to another, click on the **Local** button from the toolbar in the **File Manager**. The folder structure of the **Guest** computer is displayed in both panes.

Run a script from the File Manager

You can open, edit, and run a script while you are in the **File Manager**.

Click on the **Script Editor** button from the toolbar to open the **Script** dialog box.

Refer to the Create and run a Netop script for more information about using scripts.

2.13 Log events

To support security functions, Netop Remote Control includes an extensive event logging feature that enables you to log session activity and logon attempts to multiple logging destinations.

You can log Netop events:

- In a Netop log on the local computer.
- In the database of a central Netop Server.
- In an SNMP enabled management console (by sending SNMP traps to an SNMP enabled central management console, such as HP OpenView).

To enable logging, proceed as follows:

1. In the **Tools** menu, select **Log Setup**. The **Log Setup** windows is displayed.
 2. In the **Log Setup** tab, select where you want to log events.
 3. Click on the relevant tab to set up the logging, for example the **Netop Local** tab, if you selected **Log Locally** on the **Log Setup** tab.
 4. In the **Netop Local** tab, select the events you want to view in the list of events, all or a specific type of events.
 5. On the list of events select the individual events that you want to include in the logging.
- By default each Netop event is written to the local Netop log file immediately. Clear the Write to disk for each log entry check box to write Netop events to the local Netop log file when the Netop module is unloaded. This consumes less processor capacity.
6. Click on **OK** to close the dialog box and start logging.

NOTE: The Log file name field displays the (path and) name of the log file (default: NETOP.LOG). If no path is specified, the log file is located in the Netop configuration files folder, typically C:\ProgramData\Danware Data\C\Program Files (x86)\Netop\Netop Remote Control\<Module name>. UNC paths are not supported. Only mapped paths are supported. A new local Netop log file that is created when the Netop module is loaded overwrites the old local Netop log file with the same path and file name.

[See also](#)
[Log Setup](#)

2.14 Record sessions

For documentation purposes you can record the remote control sessions. You can choose to record sessions for a specific connection, or you can choose to record sessions for all connections.

NOTE: Recording reduces the remote control session transfer speed.

Record sessions for a specific connection

Before connecting to a **Host**

1. In the **Quick Connect** tab, click on **Connection Properties**.
2. In the **Connection Properties** dialog box, click on the **Record** tab and select the **Record remote control session** check box.
3. Click on **OK**.

When you connect to a **Host** every remote control session that you run for that specific connection are recorded.

Record sessions for all connections

To record sessions for all connections, proceed as follows:

1. In the **Tools** menu, select **Program Options**.
2. In the **Program Options** dialog box, click on the **Recording** tab.
3. Select the **Enforce recording** check box to activate session recording. Select other settings as preferred.
4. Click on **OK**. Now sessions are recorded for all connections, until you change these settings again.

See also

[Connection Properties](#)

[Program Options](#)



2.14.1 Play back session recordings




Session recordings are listed in the **Recordings** tab in the **Guest** window.

To play back a session recording

1. On the **Recordings** tab, select the session recording that you want to play back.
2. On the **Connection** menu, select **Play back session recording** to start playing back the session recording. Alternatively, double-click on the session recording to start playing back the session recording.

In the **Play back recording** window, you can use the following buttons to control the playback:

Button	Description
	Click on the Stop button to close the window.
	Click on the Pause button to pause playback. Click on this button again to resume

	playback.
	Click on the Play button to start playback or resume playback when paused. When playback has ended, this button is disabled.
	Click on the Back button to return to the beginning of the recording showing a black show area.
	Playback Speed: By default, the spin box field will show x1 indicating true speed. Click on the up/down arrows to change the playback speed by a factor x1 to x20 as shown in the spin box field.

2.15 Use a skin to see the Host button layout

A **Host**, typically a CE/Mobile device, can transfer information about its button layout to Netop **Guests** enabling Guest users to see the button layout by means of a clickable bitmap. This is called a skin.

If you run a remote control session, skins enable you to see the **Host** device and execute commands on the **Host** device by clicking buttons on the applied skin. A device may have more than one skin definition depending on its state, for example slide out keyboard, portrait and landscape orientation etc. Every time the device changes state, the **Host** sends the updated skin information to the **Guest**.

If the **Guest** does not have the skin that is necessary for a remote control session with a particular **Host**, it attempts to collect a suitable skin from the **Skin Repository Server**. If the necessary skin is not available, the **Guest** uses a default skin.

The address and port number of the **Skin Repository Server** that the **Guest** collects skins from is specified in **Program Options** on the **Skins** tab. If you click on the **View Models** button in the **Skins** tab, you can also see the skins available on the **Skin Repository Server**.

To use skins, enable the function in the **Guest Connection Properties**. Click on the **Display** tab and select options for the use of skins in the **Skin** section.

NOTE: You can design additional skins using the **Netop Skin Designer** and add them to the **Skin Repository Server**.

See also

[Connection Properties](#) (Display tab)

[Program Options](#) (Skins tab)

2.16 Multisession Support

Each Windows **Host** supports up to 24 simultaneous sessions, regardless of the communication protocol (TCP, UDP or Web Connect). However, it depends on the session type and the **Host** hardware:

- up to 24 simultaneous sessions for **Remote Control**
- up to 12 simultaneous sessions for **File Transfer** or **Tunnel**

Each Windows **Guest** supports only one session initiated from the same guest instance to the same **Host**.

2.17 Switching between whitelisted applications

While remote controlling a **Host**, if application whitelisting is enabled, only the whitelisted applications are visible and accessible in the **Guest** remote control window. This means that reaching a whitelisted application, which is behind a non-whitelisted application, is more difficult to do. In order to address this problem, there is an easy way to switch between the whitelisted applications by using the dedicated button in the **Guest's** remote control window.

The list includes only the whitelisted applications and allows you to switch to any of those applications, even if they are completely covered by other whitelisted or non-whitelisted applications.

NOTE: In order to use the Whitelisted Applications switch button, it is necessary that both the **Guest** and the **Host** are version 12.73 or above.

Refer to the [Netop Knowledge Base](#) for more information about whitelisting.

2.18 Multiple monitors support

While in a remote control session, you can dynamically change the **Host** monitor to be displayed on the screen by clicking on the **Monitors** icon from the main menu and selecting the desired monitor.

3 Getting remote support

3.1 Request help

If the **Help Request** function has been enabled on the **Host**, you can request help from a **Guest** that offers help services.

To request help, proceed as follows:

1. Click on the **Request help** button in the toolbar.

Alternatively, in the Session menu, select the **Request help** command.

If the **Host** is minimized you can request help by double-clicking the **Netop Help Request** icon in the notification area.

2. Depending on how the **Help Request** function has been set up, you may now be prompted to enter various information. The Guest user can provide you with the information you need. Enter the necessary information when prompted.

When you have entered the necessary information, your help request is delivered to the help provider, who will typically start a remote control session.

While the help request status is "**Pending**", you can choose to cancel it by clicking on the **Cancel help** button in the toolbar.

See also

[Set up Help Request on Guest and Host Program Options \(Help Request tab\)](#)
[Advanced Help Request Options](#)

3.2 Notification

You may be notified of connecting **Guests** in different ways upon connection, during connection and after connection, depending on the connection notification setup.

Upon connection

You can be notified by a sound being played or a balloon tip or a list of connecting **Guests** being displayed in the notification area in the lower right corner of the screen.

The connection list can be set to disappear after a specified number of seconds, or it can be necessary for you to specify a password to close the history list.

During connection

A sound can be played at certain intervals, the **Guest** name can be displayed in the **Host** title bar, and the **Host** icon in the notification area can be animated.

After connection

You may be notified by a balloon tip or a history list of connections in the notification area when a **Guest** disconnects.

The history list can be set to disappear after a specified number of seconds, or it can be necessary that you need to specify a password to close the history list.

NOTE: You can also be prompted to confirm Guest access, if this has been set in the **Guest Access Security** dialog box on the **Guest Access Privileges** tab.

See also

[Program Options](#) (Connection Notification tab)

[Guest Access Security](#) (Guest Access Privileges tab)

3.3 Communicate with Guest users

Netop Remote Control offers two ways in which you can communicate with Guest users while receiving remote support.

If allowed by the **Guest Access Security** settings on the **Host**, the **Guest** can start a chat or an audio-video chat with a **Host**, and the **Host** can likewise start a chat or an audio-video chat with the **Guest**.

Chat

To start a chat with a connected **Guest**, proceed as follows:

1. Click on the **Chat** button in the toolbar. Alternatively, in the **Session** menu, select **Chat**.
2. In the **Chat** dialog box, type your message.
3. Click on the **Send** button.

NOTE: You can save the chat as an `*.rtf` file for documentation purposes.

Multi chat

If the Netop **Host** allows multiple simultaneous **Guest** connections, a **Guest** that the **Guest Access Security** settings allow to act as multi **Guest** session administrator can start a multi chat with the **Host** and all of the connected **Guests**.

Audio-video chat

Audio-video chat requires audio-video equipment to be installed on both sides.

To start an audio-video chat with a connected **Guest**, proceed as follows:

Click on the **Audio-Video Chat** button on the toolbar.

Alternatively, in the **Session** menu, select **Audio-Video Chat**.

The **Audio-Video Chat** dialog box is displayed.

Depending on the hardware available, you can now use your microphone to talk to the Guest user, and if Video is enabled by the Guest user, you can also see each other in the dialog box.

Use the slide bars on the right to control sound and video.

Only the **Guest** can end the audio-video chat session.

NOTE: Each **Guest** and each **Host** can run only one audio session including Transfer Sound at a time.

See also

[Guest Access Security](#)

[Program Options](#) (Audio-Video Chat tab)

3.4 End a remote control session from a Host computer

If your computer is being remote controlled and you feel that you do not want to continue the session for whatever reason, you can end the session from the **Host**.

To end a remote control session from the **Host**, proceed as follows:

Click on the **Disconnect** button on the toolbar. Alternatively, in the **Session** menu in the Host window, select **Disconnect**.

If the **Host** is minimized and only visible as an icon in the notification area in the lower right corner of the screen, you can end the remote control session by right-clicking on the icon and selecting **Disconnect**.

4 Providing remote support

4.1 Set up Help Request on Guest and Host

If you offer help services, the **Help Request** function should be set up on both the **Guest** and **Host** before Host users can request help from your help service.

You also need to specify the communication profile or profiles to use.

To set up the **Help Request** function on the **Guest**, proceed as follows:

1. In the **Tools** menu, select **Program Options**.
2. Click on the **Help Request** tab.
3. Select the **Enable Help Request** check box.
4. In the **Help Service** tab, select the **Enable Help Service** check box.

In one of the **Help Service** fields below, specify the name of your help service. You may have more than one help service.

Setup use of tickets

If you have an extended **Guest**, you see two more sub-tabs on the **Help Request** tab.

Service Tickets tab

The **Service Tickets** tab enables an extended **Guest** to service help requests by a service ticket number. Service tickets are used for Netop Remote Control and Netop OnDemand Remote Control (1.74 and earlier versions).

1. Select the **Enable Service Tickets** check box to enable use of service tickets to service help requests by a service ticket number.

2. In the **Service Ticket Format** field enter a service ticket format using any character plus the control characters #, @, and *.

produces a number (0-9), @ produces a letter (A-Z), and * produces a number or a letter (0-9, A-Z), for example @##-****. In the **Help Request** tab in the **Guest** window, this generates service tickets that look like this: JK50-M3SR.

NOTE: The service ticket generated from this can only be used once, after which a new ticket is generated.

3. In the **Number of auto generated Service Tickets** field specify the number (0-3, 0 = manually) of service tickets to be auto-generated.

WebConnect tab

The **WebConnect** tab enables an extended **Guest** to service help requests by a WebConnect ticket. WebConnect tickets are used for Netop OnDemand Remote Control 2.0 and later versions.

1. Select the **Enable WebConnect** tickets check box to enable use of **WebConnect** tickets.
2. In the **WebConnect Ticket** field enter anything that you want to use as a WebConnect ticket for identification purposes during a help request session using WebConnect, for example an email address, a name, or a keyword, for example Security Server.
3. Select a communication profile in the **WebConnect Communication Profile** list.

The WebConnect communication profile contains the credentials and the Connection Manager URL that are in use for the WebConnect connection.

The profile itself should be defined in the **Setup Wizard** or in **Program Options > Communication Profiles** before you can select it here. One or more **WebConnect** profiles can be defined in **Communication Profiles**.

4. In the **Update interval** field, specify how often the **Netop Guest** should communicate with **WebConnect** and check for new tickets. Specify an interval in seconds.
5. Click on **OK** to close the **Program Options** dialog box.

To set up the **Help Request** function on the **Host**, proceed as follows:

1. In the **Tools** menu, select **Program Options**.
2. Click on the **Help Request** tab.
3. In the **Help provider** field, enter the name of a help service provider.
4. Specify the communication profile that should be used for the connection.

Select one of these options:

Use current Host communication profiles	<p>Select this option to send help requests using communication profiles enabled in Tools > Communication Profiles.</p> <p>If you have enabled more than one communication profile, or if you have enabled only communication profiles using networking communication devices, the Select Help Request Communication Profile dialog box is displayed when requesting help.</p> <p>Select a communication profile.</p> <p>You can only use TCP/IP, if Guest and Host are on the same network.</p> <p>If the Guest and Host are not on the same network, select</p>
---	--

	<p>for example LAN (TCP) or Internet (TCP). Make sure to specify the Guest IP address.</p>
<p>Use specific Communication Profile</p>	<p>Select this option to use a specific communication profile. Select one of the available Host communication profiles in the drop-down list.</p> <p>You can only use TCP/IP, if the Guest and Host are on the same network.</p> <p>If the Guest and Host are not on the same network, select for example LAN (TCP) or Internet (TCP). Make sure to specify the Guest IP address.</p> <p>You can specify the IP address at this point in the Advanced Help Request Options, if you prefer. Otherwise, the Host user is prompted for the IP address when requesting help. The latter allows the Host user to specify different addresses and thereby contact different supporters when requesting help.</p> <p>Advanced Help Request Options</p> <ol style="list-style-type: none"> 1. Click on the Advanced button. The Advanced Help Request Options dialog box is displayed. 2. In the Phone number or IP address field enter the IP address of the Guest. You can also change the Help request timeout if not answered setting, if necessary. 3. If you request help through a Guest network Netop Gateway, you can specify the gateway logon credentials in the Gateway logon section. Otherwise the Host user is prompted to enter these when requesting help. 4. Select the Use current logon credentials for Windows Security authentication check box, if the Host user should log on using the name, password and domain that the user used to log on to Windows on the Host computer. 5. Select the Enable Help Service check box.

4.2 Respond to a help request

If you are using service tickets (extended Guest for Remote Control OnDemand 1.74 and earlier versions) for help requests, make sure to pass on a service ticket to the Host user by phone or e-mail.

You find the service ticket in the **Guest Help Request** tab. The service ticket can only be used once, after which a new ticket is generated. The Host user then uses the service ticket to send a help request to you.

If you are using WebConnect tickets (extended Guest for Remote Control OnDemand 2.0 and later versions), you do not need to do anything.

The WebConnect ticket can either be predefined in the OnDemand **Host** or the **Host** user can enter anything, for example a name or a keyword in the OnDemand Host.

All incoming help requests are displayed in the **Guest Help Request** tab.

Double-click on a help request on the list to start a default session, which is typically remote control.

Alternatively, select a help request and click on a button from the toolbar to start a remote control session or another type of session.

You are prompted to log on to the **Host**.

Once you have logged on to the **Host**, you can start helping the Host user using the available remote control functions, and you can communicate with the Host user using the chat for example.

NOTE: To be able to service help requests make sure to set up the communication profiles and the **Help Request** options on both the **Guest** and **Host**. Refer to the [Set up Help Request on Guest and Host](#) for more information.

4.3 Run a multi Guest session

If allowed in the **General** tab of the **Host Program Options**, multiple **Guests** can connect to the same **Host** in a multi **Guest** session.

For example, if you need help from another supporter while providing support to a Host user, other **Guests** can join your session by connecting to the same **Host**.

In a multi **Guest** remote control session, one **Guest** at a time can have keyboard and mouse control. The **Guest** that has keyboard and mouse control can execute all actions allowed to it by the **Guest Access Security** settings on the **Host**.

Guests that do not have keyboard and mouse control can execute only a limited range of actions.

The **Host** window title bar displays the name of the **Guest** that has keyboard and mouse control.

Other connected **Guests** are indicated by +<Number of other connected Guests>.

Example: Connected [User1]+1

Guests that the **Guest Access Security** settings allow to act as multi **Guest** session administrator can manage a multi **Guest** session. This means that these **Guests** can:

- Show a connection list of connected **Guests**
- Suspend further connections
- Disconnect all other **Guests**
- Start a multi chat session with all connected the **Guests** and the **Host**.

Guests with no rights to act as a multi **Guest** session administrator cannot carry out these actions.

See also

[Communicate with Host users](#)

[Guest Access Security](#)

4.4 Send special keystrokes

During remote control you can send various keystroke combinations to the **Host** computer using the Send Keystrokes command on the title bar menu of the **Remote Control** window.

You also find the most commonly used commands as toolbar buttons in the **Remote Control** window.

CAUTION! Using these keystroke combinations from the keyboard can have undesired effects.

Keystroke combination	Description
Send CTRL+ESC	Select this command to send the keystroke combination CTRL+ESC to the Host . Alternatively, click on Send CTRL+ESC button on the toolbar. This keystroke combination displays the Start menu on a Windows Host computer or the Window List on an OS/2 Host computer.
Send CTRL+ALT+DEL	Select this command to send the keystroke combination CTRL+ALT+DEL to the Host . Alternatively, click on the Send CTRL+ALT+DEL button on the toolbar. This keystroke combination displays the security dialog box on a Windows 2000/XP/2003/2008/Vista/7 Host computer or restarts

	<p>an OS/2 Host computer.</p> <p>NOTE: Send Ctrl+Alt+Del is disabled with a Windows ME, 98 or 95 Host computer. Select Restart Host PC to restart the Host computer.</p>
Send ALT+TAB	<p>Select this command to send the keystroke combination ALT+TAB to the Host.</p> <p>This keystroke combination switches the active window clockwise on the Host computer screen.</p>
Send ALT+SHIFT+TAB	<p>Select this command to send the keystroke combination ALT+SHIFT+TAB to the Host.</p> <p>This keystroke combination switches the active window counter-clockwise on the Host computer screen.</p>
Send Print Screen	<p>Select this command to send a PRINT SCREEN command to the Host.</p> <p>This copies an image of the entire Host computer screen to the Host computer clipboard.</p>
Send ALT+PRINT SCREEN	<p>Select this command to send an ALT+PRINT SCREEN command to the Host.</p> <p>This copies an image of the active window on the Host computer screen to the Host computer clipboard.</p>

NOTE: The **Send Keystrokes** command is disabled if the **Guest Access Security** settings on the **Host** do not allow use of keyboard and mouse.

4.5 Use clipboard commands

During remote control you can use the clipboard.

You access the clipboard commands from the **Clipboard** command in the title bar menu of the **Remote Control** window. You also find these commands as toolbar buttons in the **Remote Control** window.

Command	Description
Send to Host	<p>Select this command to send the Guest computer clipboard content to the Host computer clipboard.</p> <p>Alternatively, click on the Send Clipboard button from the toolbar.</p> <p>NOTE: This command is disabled if the Guest Access Security set-</p>

	tings on the Host do not allow Transfer clipboard.
Retrieve from Host	Select this command to retrieve the Host computer clipboard content to the Guest computer clipboard. Alternatively, click on the Retrieve from Host button from the toolbar. NOTE: This command is disabled if the Guest Access Security settings on the Host do not allow Transfer clipboard.
Save Screen to Clipboard	Select this command to capture the Host computer screen image to the Guest computer clipboard. Alternatively, click on the Save Screen to Clipboard button from the toolbar.
Save Screen to File	Select this command to capture the Host computer screen image and save it as a bitmap file with the name <Host name>-<Date>-<Time>.bmp in the SnapShot folder. You can change the file name and folder before saving. Alternatively, click on the Save Screen to File button from the toolbar.

4.6 Communicate with Host users

Netop Remote Control offers a number of ways in which you can communicate with the Host users while providing remote support.

If allowed by the **Guest Access Security** settings on the **Host**, the **Guest** can start a chat or an audio-video chat with a **Host**, or the **Guest** can send a message to the **Host**.

Chat

To start a chat, when already connected to a **Host**, proceed as follows:

1. In the **Remote Control** window, click on the **Chat** button from the toolbar.
2. In the **Chat** dialog box, type your message.
3. Click on the **Send** button.

To start a chat, if not already connected to a **Host**, proceed as follows:

1. In the **Guest** window, select the **Host**.
2. Click on the **Chat** button from the toolbar. Alternatively, select **Chat** in the **Connection** menu.
3. In the **Chat** dialog box, type your message.
4. Click on the **Send** button.

The Host user can reply, and the chat session remains open until either you or the Host user

close it by clicking on the **End chat** button. A **Host** can also request a chat with the **Guest**.

NOTE: You can save the chat as an `*.rtf` file for documentation purposes.

Multi chat

If the **Netop Host** allows multiple simultaneous **Guest** connections, a **Guest** that the **Guest Access Security** settings allow to act as multi **Guest** session administrator can start a multi chat with the **Host** and all the connected **Guests**. Refer to the [Run a multi Guest Session](#) section for more information.

A **Start Multi Chat** button is displayed in the toolbar in the Remote Control window of the **Guest** that is a multi **Guest** session administrator. Click on this button to start a chat with the **Host** and all other connected **Guests** at the same time.

Audio-video chat

The **Guest** can start an audio-video chat session with a **Host**, if that audio-video equipment is installed on both sides. Also the **Host** can request an audio-video chat session with the **Guest**, if they are already connected.

To start an audio-video chat, when already connected to a **Host**, proceed as follows:

In the **Remote Control** window, click on the **Audio-Video Chat** button from the toolbar.

The **Audio-Video Chat** dialog box is displayed.

To start an audio-video chat, if not already connected to a **Host**, proceed as follows:

1. In the **Guest** window, select the **Host** that you want to chat with.
2. Click on the **Audio-Video Chat** button from the toolbar. Alternatively, select **Audio-Video Chat** on the **Connection** menu.

The **Audio-Video Chat** dialog box is displayed.

Depending on the hardware available, you can use your microphone to talk to the Host user, and if **Video** is enabled, you can also see each other in the dialog box.

Use the toolbar buttons at the top and the slide bars on the right to control sound and video.

Only the **Guest** can end the audio-video chat session by clicking on the **Stop Audio-Video Chat** button from the toolbar.

NOTE: Each **Guest** and each **Host** can run only one audio session including Transfer Sound at a time.

Message

To send a message to a **Host**, when already connected, proceed as follows:

1. In the **Remote Control** window, click on the **Send Message** button from the toolbar.
2. Type the text you want to send and click on the **Send Message** button from the toolbar.

To send a message to a **Host**, if not already connected, proceed as follows:

1. Select the **Host**.
2. Click on the **Send Message** button from the toolbar. Alternatively, select **Send Message** in the **Connection** menu.
3. Type the text you want to send and click on the **Send Message** button from the toolbar.

The message is displayed on the **Host** computer. The Host user cannot reply or send a new message. If you want the Host user to reply, use one of the chat options.

See also

[Guest Access Security](#)

[Program Options](#) (Audio-Video Chat tab)

4.7 Send or receive print jobs

You can send a **Guest** computer print job to a **Host** computer printer (remote printer). Host users can likewise send a print job to a **Guest** computer printer.

A Netop printer and the correct remote printing device driver must be installed on the computer sending the print job.

To add a Netop printer on the **Guest** computer, proceed as follows:

1. In the **Tools** menu, select **Options**.
2. Click on the **Remote Printing** tab.
3. Click on the **Add** printer button. The **Add printer guidelines** window is displayed.
4. Read the guidelines and click on the **Ready** button to start adding a Netop printer using the **Add Printer Wizard**.

The **Add printer guidelines** window remains on the screen while you go through the wizard.

Send a print job to a remote printer

Once you have added a Netop printer on the **Guest** computer, you can send a print job to the remote printer in question.

Example: If you want to print a Word document on the remote printer, activate the print job as you normally would in Word. Make sure that you choose the Netop printer that you added.

4.7.1 Redirect a print job

You can redirect a print job sent from the Host computer to the **Guest** computer to any printer specified on the **Guest** computer.

To redirect a print job, proceed as follows:

1. In the **Tools** menu, select **Options**.
2. Click on the **Remote Printing** tab.
3. In the **Redirect print to** section, select one of the following options:

Option	Description
Default printer	Redirect the print job to the default Guest computer printer.
Prompt with a list of available printers	Select this option and click on the Browse button to display the Select Print Redirection Printer dialog box. The dialog box contains the names of Guest computer printers. Select a name and click on OK to specify the printer name in the field. Incoming Netop print jobs are then redirected to this printer.

4.8 Share your screen

When providing support you might want to demonstrate a procedure to a **Host** user.

If allowed by the **Guest Access Security** settings on the **Host**, you can start a demonstrate session with a **Host**. This enables you to display the **Guest** computer screen image on the Host computer while you are carrying out a particular procedure.

To start a demonstrate session, proceed as follows:

When already connected, in the **Remote Control** window, click on the **Demonstrate** button on the toolbar.

If you are not already connected, you can connect and run a demonstrate session from the **Phonebook** tab, the **Quick Connect** tab, or the **History** tab.

1. In one of the these tabs, select the **Host** computer that you want to connect to and run a demonstrate session with.

2. Then click on the **Demonstrate** button in the toolbar in the **Guest** window.

When you start the demonstrate session, and before anything is displayed on the **Host** computer, the **Mask Windows** dialog box is displayed. This dialog box enables you to mask **Guest** computer screen elements that you do not want the Host user to see. These elements are displayed as black rectangles on the **Host** computer screen.

To mask/unmask a screen element, proceed as follows:

1. Select the element in the pane.
2. Click on the **+** (plus) or **-** (minus) button at the bottom of the dialog box to mask or unmask the element.

Select the **New screen** window warning check box to have the **New window** dialog box displayed if a new screen element that does not belong to a masked application element opens on the **Guest** computer screen.

Select what you want to mask.

3. Click on **OK**.

The Netop Demonstration window is displayed on the selected **Host** computer screen.

During a demonstrate session, a small toolbox is displayed on the **Guest** computer screen. It allows you to stop the demonstration or display the **Mask windows** dialog box, if you want to make changes to the masking.

4.9 Netop Screen Video

Netop Screen Video is a tool for recording the actions you take and the commands you click.

To start **Netop Screen Video**, proceed as follows:

In the Windows **Start** menu, point to **All Programs, Netop Remote Control, Tools** and then click on **Screen Video**.

Use the tool to create a video within an area of the screen or of the entire screen.

To capture a screen video

1. Set up the tool according to your preferences.

In the **Region** menu, select the area you want to capture.

TIP: Typically **Full Screen** is selected.

In the **Options** menu, select recording options and define settings.

TIP: It is often a good idea to hide the program when recording starts, and to define keyboard

shortcut keys to start and stop the recording.

These settings are saved and can be used the next time you want to capture a screen video.

2. To start the recording, click on the **Record** button
3. Stop recording by pressing the shortcut key you defined. Alternatively, you can right-click on the **Netop Screen Video** icon in the notification area and click on the **Stop** button on the short-cut menu.

Overview of the Options menu

Option	Description												
Video Options	<p>Change the encoder to be used for the video recording. For the configurable encoders, click on Configure to set for example compression.</p> <p>Move the Quality slider to the right to increase quality. Note that a higher quality video file will be larger.</p> <p>You can let Netop Screen Video automatically adjust frame rates: Leave the Auto Adjust check box selected.</p> <p>Or you can clear the Auto Adjust check box and set the options yourself:</p> <p>Max frame rate left end represents recording 200 frames/second and Max frame rate right end represents recording 1 frame/minute. When you move the slider, the Set Key Frames Every, Capture Frames Every and Playback Rate fields are automatically adjusted:</p> <table border="1" data-bbox="528 1317 1407 1630"> <thead> <tr> <th data-bbox="528 1317 746 1417">Recording frame rate</th> <th data-bbox="751 1317 970 1417">Set Key Frames Every</th> <th data-bbox="975 1317 1193 1417">Capture Frame Every</th> <th data-bbox="1198 1317 1407 1417">Playback Rate</th> </tr> </thead> <tbody> <tr> <td data-bbox="528 1424 746 1525">200 - 1 frames/second</td> <td data-bbox="751 1424 970 1525">Second</td> <td data-bbox="975 1424 1193 1525">0.005 - 1 second</td> <td data-bbox="1198 1424 1407 1525">Recording frame rate</td> </tr> <tr> <td data-bbox="528 1532 746 1630">60 - 1 frames/minute</td> <td data-bbox="751 1532 970 1630">20 frames</td> <td data-bbox="975 1532 1193 1630">1 - 60 seconds</td> <td data-bbox="1198 1532 1407 1630">20 frames/second</td> </tr> </tbody> </table> <p>NOTE: Playback is synchronized at each key frame. A large number of frames makes a large file.</p>	Recording frame rate	Set Key Frames Every	Capture Frame Every	Playback Rate	200 - 1 frames/second	Second	0.005 - 1 second	Recording frame rate	60 - 1 frames/minute	20 frames	1 - 60 seconds	20 frames/second
Recording frame rate	Set Key Frames Every	Capture Frame Every	Playback Rate										
200 - 1 frames/second	Second	0.005 - 1 second	Recording frame rate										
60 - 1 frames/minute	20 frames	1 - 60 seconds	20 frames/second										
Cursor Options	Define whether the mouse pointer should be included in the recording, and define the pointer appearance.												
Audio Options	Define options for recording sound as well as video.												
Autopan Speed	Setting autopan speed is relevant when Enable Autopan has been selected (command above in the same menu). Automatic panning												

	<p>means that the recording region center is automatically moved towards the mouse pointer position while recording. When Enable Autopan is not selected, the recording region center does not move.</p> <p>Autopan Speed defines how fast the recording region center is moved.</p>
Recording Thread Priority	<p>Recording Thread Priority means that a priority is set for use of computer resources for Netop Screen Video as compared to other program running at the same time.</p> <p>General guideline: If the video recording does not play smoothly, computer resources may be too scarce and it might help to raise the Recording Thread Priority.</p>
Keyboard Shortcuts	Define keyboard keys to control the recording.

4.10 Netop Marker Utility

Use the **Netop Marker Utility** to draw and write or magnify something on the **Host** computer screen during a remote control session.

The tool can be used by both the **Guest** computer and the **Host** computer. Note, though, that the Host user cannot initiate this feature. It only opens if the **Host** is remote controlled and the Guest user decides to start the Marker Utility.

The texts and lines created using the Netop Marker Utility 'float' over the desktop. If other applications are opened, texts and lines remain on top.

The **Netop Marker Utility** includes tools for drawing shapes like circles and rectangles and for writing text or magnifying a part of the screen.

To start the **Netop Marker Utility** from the **Netop Guest**, proceed as follows:

1. Connect to the **Host**.
2. In the **Remote Control** window, click on the **Marker Mode** button in the toolbar.

The **Netop Marker Utility** opens and you can start using the tools. Place the mouse pointer on a toolbar button for a description of the tool.

To close the **Netop Marker Utility** from the **Guest**, proceed as follows:

In the **Remote Control** window, click on the **Marker Mode** button in the toolbar.

Alternatively, in the title bar menu of the **Remote Control** window, select the **Marker Mode** command.

5 Dialog box help

5.1 Guest dialog boxes

5.1.1 Advanced audio settings

Use the **Advanced audio settings** dialog box to specify preferred audio playback and recording devices to be used in connection with audio-video chat.

Playback

The **Preferred device** drop-down list contains the names of audio playback devices found by Windows. Select your preferred audio playback device from the list.

Record

The **Preferred device** drop-down list contains the names of audio recording devices found by Windows. Select your preferred audio recording device in the list.

NOTE: If multimedia devices are connected to the computer, the `<Use any available device>` selection may select a connected device instead of the computer sound system. In that case, select the computer sound system.

Audio Compression

The Try audio compression codecs in the following order pane contains a Windows prioritized list of mono audio compression codecs available on the **Guest** computer.

Use the **Up/Down** buttons to move a codec up or down in the prioritized list. You can restore the default codec priority by clicking on the **Use defaults** button.

The highest prioritized **Guest** computer codec that is also available on the **Host** computer is used.

See also

[Program Options](#) (Audio-Video Chat tab)

5.1.2 Advanced Help Service

Use the **Advanced Help Service** dialog box to specify actions to be executed when a help request arrives.

Option	Description
Action	<p>Select an action in the list.</p> <p>The list contains the following options:</p> <ul style="list-style-type: none"> • None: No action. • Send message: Run a local program if specified and send a message to the Host. The fields below are enabled. • Run local program: Run a local program if specified. The fields below, except Send message, are enabled.
Command line	<p>Specify the command line of a Guest computer program, typically a helpdesk program to register the help request. Click on the [...] button to select a program file.</p> <p>You can add the following arguments to the command:</p> <ul style="list-style-type: none"> • %H: Help request Host name. • %T: Help request time. • %P: Help request problem description.
Timeout	<p>Specify a number of seconds (default: 5, range 0-9999, 0 = no timeout). The command specified above times out (cancels if unsuccessful) after the specified number of seconds.</p>
Send message	<p>Specify the path and name of an *.rtf file to send a message with the *.rtf file content to the Host requesting help. See also Communicate with Host users (Message).</p> <p>Click on the [...] button to open an .rtf file.</p>
Clear help request	<p>Select this check box to delete the help request record in the Help Request tab when the actions specified above have been executed successfully.</p> <p>NOTE: Deleting the Help Request tab record does not cancel the help request.</p>
Display a notification message when new help request arrives	<p>Select this check box to be notified when a help request arrives.</p> <p>The notification message contains the help request Host name, time and, if specified, problem description.</p>

See also

[Set up Help Request on Guest and Host](#)

[Respond to a help request](#)

[Program Options](#) (Help Request tab)

5.1.3 Advanced inventory option

Use the **Advanced inventory option** dialog box to specify inventory processing and custom inventory items.

Run program after inventory scan

You can specify an inventory processing program to automatically process each newly retrieved Host computer inventory. Select one of these options:

Option	Description
Disable	Disable running the program specified below.
Run for each Host	Run the program specified below when a Host computer inventory is retrieved.
Run after all scans have completed	Run the program file specified below when a batch of Host computer inventories is retrieved.
File name	Specify an inventory processing program file path and name including required command line switches. Click on the Browse button to open an inventory processing program file. The path and name of the file is displayed in the field.

Custom inventory items

To add custom inventory items, click on the **Add** button. The **Custom Inventory Items** dialog box is displayed. Refer to the [Custom Inventory Items](#) for more information.

To edit a custom inventory item after adding it, click on the **Edit** button if you want.

When you generate **Host** inventories, the inventories contains the custom inventory item that you defined.

See also

[Program Options](#) (Inventory tab)

5.1.4 Advanced TCP/IP Configuration

Use the **Advanced TCP/IP Configuration** dialog box to set advanced options for the TCP/IP communication profile.

Bindings

Option	Description
Use all available IP addresses	Select this check box to use all available IP addresses. If the computer has multiple IP addresses and only one of them is to be used for Netop communication, clear the check box to enable the IP address field or interface list.
IP address	Specify the IP address that is to be used for Netop communication.
Use an interface	Specify which network interface is to be used for Netop communication.

Specify Port Numbers

Option	Description
Use default port numbers	Select this check box to use the default Netop port number 6502 for Receive port and Send port . Port number 1970 is officially registered to Netop Remote Control. However, port number 6502 is the preferred default port number for compatibility with older Netop versions.
Receive port	If the Use default port numbers check box is selected, the port number 6502 is displayed. If the Use default port numbers check box is not selected, the number is editable. You can specify a number in the range 1025-65535.
Send port	If the Use default port numbers check box is selected, the number 6502 is displayed. If the Use default port numbers check box is not selected, the number is editable. You can specify a number in the range 1025-65535. The Send port number of the source module should correspond to the Receive port number of the destination module.

Options

Select the **Use TCP for session if possible** check box to connect by TCP/IP, but if available on **Guest** and **Host**, switch to TCP/IP (TCP) when connected for high speed session communication.

Netop Name Server

Option	Description
Use Netop Name Server	Select this check box to use Netop Name Server to resolve Netop names into IP addresses. Using Netop Name Server will facilitate connecting across segmented IP networks including the Internet.
Primary	Use the default name <code>nns1.netop.com</code> of the primary public Netop Name Server on the Internet, or specify the IP address or DNS name of a primary Netop Name Server on your corporate network.
Secondary	Use the default name <code>nns2.netop.dk</code> of the secondary public Netop Name Server on the Internet, or specify the IP address or DNS name of a secondary Netop Name Server on your corporate network.
Ignore port information from Name Server	Select this check box to replace the destination module Receive port number received from Netop Name Server by the port number specified below. NOTE: Some types of firewalls replace sent Receive port numbers by invalid port numbers to protect network computers against connection attempts. In that case, Netop Name Server receives, stores and returns invalid Receive port numbers, which are necessary to be replaced by valid Receive port numbers.
Use Port	Specify the port number that should replace the Receive port number received from the Netop Name Server . NOTE: To use the Netop Name Server , specify the applicable Name Space ID under Tools > Program Options > Host Name > Netop Name Server .

See also

[Communication Profile Edit](#)

5.1.5 Advanced Video

To set advanced video options, use the **Advanced Video** dialog box.

Select the driver to use for video in the drop-down list. If a video camera is installed, the field contains its driver name, and the image frame displays the image captured by the camera.

To display the **Windows Video Format** dialog box and format the video capture image, click on the **Format** button .

To display the **Windows Video Source** dialog box and change video source properties, click on the **Properties** button .

To disable video data compression, select the **Disable compression** check box.

5.1.6 Communication Profile Edit

Use the **Communication Profile Edit** dialog box to create or edit a communication profile.

Communication information

Option	Description
Description of the communication profile	<p>Enter a communication profile name. The name should be unique.</p> <p>If the field already contains a communication profile name, you can edit the field contents.</p> <p>NOTE: You can create multiple differently named communication profiles that use the same communication device.</p>
Communication device	<p>Specify the name of the communication device to be used by the communication profile.</p> <p>Select a communication device on the drop-down list.</p>
Use dial-up networking	<p>This check box is enabled only if a TCP/IP family communication device is selected from the Communication device field.</p> <p>Select the check box to expand the Communication Profile Edit dialog box with a Dial-up network connection section.</p>

Dial-Up Network Connection

Option	Description
Dial-up network profile	On the list of available dial-up network profiles, select a profile to use to connect to a network.
Dialing from Calling card	The dialing properties of the selected dial-up network profile is displayed here.
Configure	Click on this button to display the Dial-up Connection dialog box and configure the dial-up connection.
Dialing properties	Click on this button to display the Phone and Modem Options dialog

	box and edit the dialing properties of the selected dial-up network profile.
Add profile	Click on this button to display the Network Connection Wizard , which helps you add a dial-up network profile.

[Communication profile name]

The lower dialog box section is named according to the communication device displayed in the **Communication device** field.

In this section, you can specify the configuration of the communication device that should apply to the communication profile. The options vary depending on the communication device.

For more information about the most commonly used communication devices see the list below.

TCP/IP

Max packet size (MTU)	Specify the maximum packet size (range 512- 5146, default: 2600). A high MTU increases the communication speed and a low MTU can contribute to solving communication problems.
Optimize for Internet communication	Select this check box to apply settings (MTU, data compression, etc.) optimized for communicating across the Internet.
Advanced	Click on this button to display the Advanced TCP/IP Configuration dialog box. See Advanced TCP/IP Configuration .
IP Broadcast list	Click on this button to display the IP Broadcast List dialog box. See IP Broadcast List .

General information about Netop TCP/IP

Netop TCP/IP is a UDP based communication device that connects by UDP and optionally communicate by TCP/IP (TCP) during a session.

Each communication profile that uses TCP/IP can support multiple Netop connections.

TCP/IP offers three connect options:

- IP address
- Name response
- Name resolution

IP address

You can connect by IP address across segmented IP networks including the Internet. It is necessary that the source module port number matches the destination module port number, see Advanced TCP/IP Configuration.

If you connect from outside a network protected by a network address translation (NAT) firewall or proxy server to a Netop module on a network computer, specify the firewall or proxy server public IP address with the port number assigned to the network computer, for example 192.168.20.51:1234.

Ask the firewall or proxy server administrator which port number is assigned to a specific network computer.

Name response

Name response broadcasts a name, the first characters of a name or without a name, requesting Netop modules with a corresponding enabled name to respond. The following name response options are available:

- If a **Guest** connects or browses using the Host name qualifier H::, the Host can respond by its enabled Netop Name type name.
- If a **Guest** connects or browses using the Host name qualifier U::, the Host can respond by its enabled LAN User type name.
- If a **Host** requests help, the **Guest** can respond by its enabled Help service names.

NOTE: A broadcast reaches only computers on the local network segment and computers whose IP address or DNS name is specified in the communication profile **IP Broadcast List**.

Name resolution

Name resolution resolves a specified name into its corresponding IP address. These name resolution options are available:

- In the Advanced TCP/IP Configuration dialog box, select the Use Netop Name Server check box and specify the Netop Name Servers to use.

Under **Program Options > Host Name > Netop Name Server**, specify the **Name Space ID** used by the Netop modules you want to connect to.

Connect by any enabled destination module name, for a **Host** help request a Guest Help service name.

Netop Name Server resolves the name into the corresponding IP address and connect by it across segmented IP networks including the Internet. You can also browse for Hosts using the

Netop Name Server.

- If a **Guest** connects by a name using the Host name qualifier DNS::, a domain name server interprets the name as a DNS name and attempt to resolve it into a corresponding IP address, so the **Guest** can connect by it across segmented IP networks, including the Internet.

NOTE: In most cases, if the Host name qualifier H:: is used, a domain name server interprets the name as a DNS name and attempt to resolve it into a corresponding IP address.

- If a **Guest** connects by a name using the Host name qualifier LDAP::, the **Guest** searches directory services specified on the **Directory Services** tab in the **Program Options** dialog box for a user with this name and connect by the corresponding address attribute, which is typically an IP address.

You can also browse for Hosts using directory services.

See also

[Program Options](#) (Host Name tab)

Connect problems

In case of connect problems, verify that an IP connection is available from a command prompt by typing:

```
PING <Netop module IP address>
```

The PING utility sends four data packets requesting a reply. If you receive the replies, an IP connection is available.

If an IP connection is available and connectivity problems persist, consult your network/system administrator or submit a support request to Netop Support.

TCP/IP (TCP)

Option	Description
Optimize for Internet communication	Select this check box to apply settings (MTU, data compression, etc.) optimized for communicating across the Internet.
Encapsulate in HTTP	Select this check box to wrap data packets as HTTP packets to ease firewall passage. This is also known as HTTP-tunneling.
Use Proxy Settings	If you select Encapsulate in HTTP , the Use Proxy Settings check box becomes available for selection. If you select this check box, proxy authentication is activated in the used communication profile. The application uses the proxy settings defined in

	Windows.
Advanced	Click on this button to display the Advanced TCP/IP Configuration dialog box. See Advanced TCP/IP Configuration .

Netop TCP/IP (TCP) is a TCP based communication device.

Each communication profile that uses TCP/IP (TCP) can support one Netop connection. To support multiple Netop connections, you can create multiple communication profiles that use TCP/IP (TCP).

To connect, specify a computer IP address.

If you connect from outside a network protected by a network address translation (NAT) firewall or proxy server to a Netop module on a network computer, specify the firewall or proxy server public IP address with the port number assigned to the network computer, for example 192.168.20.51:1234.

Ask the firewall or proxy server administrator which port number is assigned to a specific network computer.

- If a **Guest** connects directly to a **Host**, specify the **Host** computer IP address.
- If a **Guest** connects through a remote network **Netop Gateway** to a **Host**, specify the IP address of the gateway computer and optionally the **Host** name.
- If a **Host** requests help, a **Guest** connected to directly or on a remote Netop Gateway network can respond by its enabled Help service names.

TCP/IP (TCP IPv6)

Option	Description
Optimize for Internet communication	Check this box to apply settings (MTU, data compression, etc.) optimized for communicating across the Internet.
Advanced	Click on this button to display the Advanced TCP/IP Configuration dialog box. See Advanced TCP/IP Configuration.

Netop TCP/IP (TCP IPv6) is a TCP IPv6 based communication device.

Each communication profile that uses TCP/IP (TCP IPv6) can support one Netop connection. To support multiple Netop connections, you can create multiple communication profiles that use TCP/IP (TCP IPv6).

You can use TCP/IP (TCP IPv6) only between computers connected to an IPv6 network.

To connect, specify a computer IPv6 address.

- If a **Guest** connects directly to a **Host**, specify the **Host** computer IPv6 address.
- If a **Guest** connects through a remote network Netop Gateway to a Host, specify the Gateway computer IPv6 address and optionally the **Host** name.
- If a **Host** requests help, a **Guest** connected to directly or on a remote Netop Gateway network can respond by its enabled Help service names.

WebConnect

Option	Description
Address	Specify the URL of the WebConnect / WebConnect 3 service, i.e. the Connection Manager, that facilitates the WebConnect / WebConnect 3 connection.
Account	Specify a WebConnect / WebConnect 3 service recognized account.
Password	Specify the password corresponding to the WebConnect / WebConnect 3 service recognized account
Domain	Specify the domain corresponding to the WebConnect /WebConnect 3 service recognized account.
Optimize for Internet communication	Select this check box to apply settings (MTU, data compression, etc.) optimized for communicating across the Internet.
Advanced	Click on this button to display the Advanced TCP/IP Configuration dialog box. See Advanced TCP/IP Configuration .
Test	Click on the Test button to verify the WebConnect Service URL.

WebConnect is a Netop proprietary communication device that enables networked Netop modules to connect easily over the Internet through a Netop connection service called WebConnect without the need to open firewalls for incoming traffic. All of the traffic is outgoing.

NOTE: **WebConnect 3** service has improved security.

Netop Portal

Option	Description
Address	Specify the address of the Netop Portal : <code>portal.netop.com</code> .
Live Update (Guest only)	Select this check box to see the available hosts in real-time.

Enrollment Key (Host only)	This is retrieved from the Netop Portal under Account > Deployments . It is a string which is associated to a deployment package. The Host is enrolled into the Netop Portal with the predefined settings from the specific deployment package. For more details on deployment packages and enrollment keys, see the Netop Remote Control Portal User's Guide .
Test	Click on the Test button to verify the Netop Portal address and credentials.

The **Netop Portal** is a service which provides connectivity across the internet. It does not require direct visibility between end points.

To remote control a **Host** using the **Netop Portal** authentication and authorization you need to:

1. Make sure that you have a **Netop Portal** account.
2. On the **Host** create a Netop Portal communication profile using the portal address and the enrollment key.
3. On the **Guest** select the **Netop Portal** communication profile. When initializing the **Netop Portal** communication profile for the first time, you are prompted to enter the **Netop Portal** credentials
4. Select the **Host**.
5. Click on the **Connect** button.

Gateway

Option	Description
Access Gateway via communication profile	In the drop-down list, select the communication profile that should be used to access the local network Netop Gateway. Select <Any initialized communication> to connect to or browse for Gateway device groups using any enabled communication profile that uses a networking communication device. Select another communication profile to connect or browse using only that communication profile, which does not need to be enabled. Select Terminal Server only if your Netop module is located on a terminal server client.
Gateway device group	Gateway device groups are administrator specified names of

	<p>available outgoing communication on local network Netop Gateways.</p> <p>Select one of these options:</p> <p>Use device group: Select this option to specify a Gateway device group name in the field.</p> <p>Browse for device groups: Select this option to display the Gateway Device Group List dialog box when connecting.</p>
--	--

Gateway is a Netop proprietary communication device that enables a network Netop module to connect through a local network Netop Gateway.

Each communication profile that uses Gateway can support only one Netop connection.

To connect, specify a modem telephone number or computer IP address according to the selected device group type. The device group type is selected in the **Gateway Device Group List** dialog box.

- If a **Guest** connects through a local network Netop Gateway directly to a **Host**, specify the modem telephone number or computer IP address of the **Host** computer.
- If a **Guest** connects through a local network Netop Gateway through a remote network Netop Gateway to a **Host**, specify the Gateway computer modem telephone number or computer IP address and optionally the Host name.
- If a **Host** requests help through a local network Netop Gateway, a **Guest** connected to directly or on a remote Netop Gateway network can respond by its enabled Help service names.

Resources

To use Gateway, make sure that one or multiple outgoing Netop Gateways run on the local network.

Terminal Server

Terminal Server is a Netop proprietary communication device that enables Netop modules running in a terminal server environment to communicate.

Each communication profile that uses Terminal Server can support multiple Netop connections.

To connect, specify a name by which the destination Netop module can respond:

- If a **Guest** connects or browses using the Host name qualifier H::, the **Host** can respond by its enabled Netop Name type name.
 - If a **Guest** connects or browses using the Host name qualifier U::, the **Host** can respond by its enabled LAN User type name.
-

- If a **Host** requests help, a **Guest** can respond by its enabled Help service names.

If the Netop Gateway runs on the terminal server console, terminal server Netop modules and Netop modules outside the terminal server environment can connect through it. Refer to the [Administrator's Guide](#) for more information.

5.1.7 Communication Profile Setup

For Netop modules to be able to communicate with each other, it is necessary for you to define a communication profile. A communication profile is a specific configuration of a communication device.

A communication device is a Netop adaptation of a generally available communication protocol or a Netop proprietary communication protocol.

A newly installed Netop module includes default communication profiles. You typically need to modify the default communication profiles or create communication profiles to optimize communication in your environment.

Use the **Communication Profile Setup** dialog box to enable/disable, create, edit and delete communication profiles.

Select check boxes in the **Communication Profile List** to enable communication profiles at Netop module loading.

Click on the **New** button to create a communication profile. The **Communication Profile Edit** dialog box is displayed.

If you want to edit a communication profile, select the communication profile and click on the **Edit** button. The **Communication Profile Edit** dialog box is displayed.

NOTE: To apply changes to enabled communication profiles, reload the **Guest**.

See also
[Communication Profile Edit](#)

5.1.8 Connect to Host

Use the **Connect to Host** dialog box to add or edit a **Connect** command.

Select how you want to connect in the **Connect** using list:

Option	Description
Phonebook file	Connect to a Host using its Netop phonebook file.
Communication profile	Connect to a Host using a communication profile and a Host name and/or a Host computer telephone number or IP address.
Local	Connect locally to the Guest computer.

The dialog box changes depending on what you select in the **Connect** using list.

- If you select **Phonebook** file, you can specify a phonebook file by browsing for it or entering the path and name of a file in the **Phonebook** file field.
- If you select **Communication profile**, specify the following:

Option	Description
Communication profile	Select a communication profile in the drop-down list which contains available Guest communication profiles.
<Host connect information>	Specify Host connect information in one or two fields according to the communication profile selection above. In a field in which you can specify an IP address, you can also specify an IP address range, e.g. 192.168.1.1-192.168.1.5, to connect to multiple Host computers from one script. In this case the logon information below must be the same for all Hosts that you specify.
Logon name	Specify any logon name required by the Host .
Logon password	Specify the corresponding password.
Logon domain	Specify the corresponding domain or directory server.
Use current logon credentials for Windows Security authentication	Select this check box to log on to the Host by the Windows logon user credentials of the Guest computer user.

- If you select **Local**, no further specification is required.

Click on **OK** to add the **Connect** command in the upper pane of the **Script** dialog box.

See also
[Script](#)

[Create and run a script](#)

5.1.8.1 Connection Properties

Use the **Connection Properties** dialog box to set a number of properties to optimize **Host** connections according to user preferences. The properties are applied individually to **Host** connections.

Connect tab

Host PC Information

Option	Description
Description	Identifies the Host record. The field can be empty. You can leave it empty to automatically specify the applicable Host name or phone number/IP address in it when creating the Host record. You can edit the field contents.
Phone number/IP address	This field is included if the communication profile selected in the Communication section uses a point-to-point, gateway, or network point-to-point communication device. Specify the Host telephone number or IP address if connecting directly to the Host , otherwise the telephone number or IP address of the network connecting Netop Gateway for the Host .
Name	If the field label does not include "(optional with Gateway)", specify the name by which the Host should respond. If the field label includes "(optional with Gateway)", you can either leave the field empty to browse for Hosts or specify the name by which the Host should respond.
Comments	Specify a comment to be displayed in the Comment column of the right pane of the Phonebook tab or the History tab.

Communication

Option	Description
Communication profile	Specifies the selected communication profile name. You can change the communication profile name by selecting another communication profile in the drop-down list.
Wake on LAN MAC address	If Wake on LAN is enabled, you can specify the MAC address of the

dress	Host computer network card to be able to start the Host computer by connecting to the Host .
-------	--

NOTE: The **Connect** tab is only included if you open the **Connection Properties** dialog box from the **Phonebook** tab or the **History** tab.

Logon tab

Use the **Logon** tab to specify **Host** and Host network connecting Gateway logon credentials in order to connect without being prompted for logon credentials.

Depending on the Guest access method defined on the **Host**, define the credentials as follows:

Guest access method	Logon name	Logon password	Logon domain
Default access privileges	Empty	Password	Empty
Netop authentication	Guest ID	Password	Empty
Windows security management*	Domain\User-name	Password	Empty
Directory services	Username	Password	Directory Service Name
Netop Portal**	N/a	N/a	N/a
NSS - Windows username & password	Domain\User-name	Password	Empty
NSS - Netop Guest ID & Password	Guest ID	Password	Empty
NSS - RSA	N/a	N/a	N/a
NSS - Directory services	Username	Password	Directory Service Name

*When authenticating to a **Host** configured to use Windows authentication, the domain is now integrated in the username field and is only needed if authenticating to a domain.

The domain field is inferred from the username when a “\” character is provided, otherwise the local computer is assumed. Examples of accepted entries in a username field are:

Username field	Host in a domain	Host NOT in a domain
Domain\username	Login OK	Login Error
Computer\username	Login OK	Login OK
.username	Login OK	Login OK
\username	Login OK	Login OK
username	Login Error	Login OK

: If the **Guest and **Host** are version 12.60 or higher and the communication profile used is based on the **Netop Portal**, the logon credentials do not work.

Select the **Use current logon credentials for Windows Security authentication** check box to log in using the Windows logon user name, password and domain of the **Guest** computer user.

NOTE: The **Logon** tab is not included if you open the **Connection Properties** dialog box from the **Remote Control** window.

Protect Item tab

Use the **Protect Item** tab to protect a **Host** record and file with a password.

Password characters are displayed as asterisks or dots. Leave fields empty to disable password protection.

Select the **Connect without password** checkbox if you want the **Guest** user to be able to use a phonebook record without knowing the password. The password protection is applied to the contents of the connection properties, so that these are protected against being changed unintentionally.

NOTE: The **Protect Item** tab is only included if you open the **Connection Properties** dialog box from the **Phonebook** tab or the **History** tab.

Startup tab

Use the **Startup** tab to set startup properties for remote control sessions.

Host window startup size

Option	Description
Windowed	Display the Host screen image in a Remote Control window. If Fit window to Host screen is selected on the Display tab, the window can be resized to its maximized size.
Full screen	Display the Host screen image in full screen to cover the entire Guest computer screen.
Maximized	Display the Host screen image in a maximized Remote Control window covering the entire Guest computer screen except the Windows taskbar.
Minimized	Display the Remote Control window as a button on the Windows taskbar.

Monitors

This section allows you to select which monitors are displayed before connecting to the **Host**.

Option	Description
All monitors	Displays all Host monitors. This is the default setting; if you do not select which Host monitor to display, when remote controlling the Host , all Host monitors are displayed on the screen.
Primary monitor	Displays the Host monitor which is set as the primary monitor.
Monitor: <monitor number>	Monitor: <monitor number>

Displays the selected **Host** monitor. If the <monitor number> is higher than the number of monitors available on the **Host**, when remote controlling the **Host** All monitors are displayed on the screen.

Remote control window startup size

Option	Description
Enable	Select this check box to enable the elements below and apply their values at startup. Leave unchecked to apply the last displayed Remote Control window position and size.
x	Specify the horizontal offset in pixels of the upper left corner of the Remote Control window from the upper left corner of the Guest computer screen at startup.
y	Specify the vertical offset in pixels of the upper left corner of the Remote Control window from the upper left corner of the Guest computer screen at startup.
Width	Specify the width in pixels of the Remote Control window at startup.
Height	Specify the height in pixels of the Remote Control window at startup.

Actions

Option	Description
Lock Host keyboard and mouse	Select this check box to disable the Host computer keyboard and mouse at startup.
Blank Host display	Select this check box to display a black screen image to the Host user at startup.
Transfer sound	Select this check box to transfer Host computer application

	sound at startup.
Suspend other Guests from connecting to Host	Select this check box to deny further Guests access to the Host at startup.

NOTE: The **Startup** tab is not included if you open the **Connection Properties** dialog box from the **Remote Control** window.

Display tab

Use the **Display** tab to set display properties for the **Host** screen image.

Host window fit

Option	Description
Fit window to Host screen	Resize the Remote Control window to fit the 1:1 scale Host screen image. If the Host screen image has more pixels than the display area of the maximized Remote Control window, the Remote Control window has scrollbars.
Fit Host screen to window	Scale the Host screen image to fit within the Remote Control window.
Do not fit	Display the part of the 1:1 scale Host screen image that fits within the Remote Control window. If the Host screen image has fewer pixels than the display area, black borders surround it. If the Host screen image has more pixels than the display area, the Remote Control window has scrollbars.

Limit number of colors in bitmap mode

Option	Description
No, use actual number of colors	Display true colors. Consumes the most transmission bandwidth.
Max 256 colors	Displays reduced palette colors. Consumes less transmission bandwidth.
Max 16 colors	Displays crude colors. Consumes little transmission bandwidth.
Max 2 colors	Displays black and white colors. Consumes a of minimum transmission bandwidth.

DOS Box Font

During remote control, if you start a command prompt window on the **Host** computer, the command prompt window characters are by default displayed on the **Guest** computer using the default font of the **Guest** computer system. You can change the font used.

Clear the **System default** check box to allow selection of another font.

Click on the **Select Font** button to select the command prompt window font. The font change is only seen when displaying the command prompt window in full screen.

Skin

In the **Display** tab of the Guest **Connections Properties** you can define how you want the Guest to use skins on connection.

Option	Description
Automatic	Select this option to enable automatic use of skin. The Host device, typically a CE/Mobile device, sends a string ID to the Guest, and the Guest contacts the Skin Repository Server to get the corresponding skin. If the Guest does not find the corresponding skin on the Skin Repository Server a default skin is used.
Do not use skin	Select this option not to use skins for remote control sessions.
Use specific skin model	Select this option, if you want to overrule the Automatic option and use a specific skin model. If you select this option, the Select Model button is activated. Click on the Select Model button to open the Skin Models window and select the skin that you want to use. In the List of Models , select the skin and then click on OK .
Show as transparent window	The skin is displayed as a transparent window without frame or background, showing only the device itself (default). If you clear the check box, you see a normal window with frame and a white background behind the device.

See also

[Use a skin to see the Host button Program Options](#) (Skins tab)

Keyboard/Mouse tab

Use the Keyboard/Mouse tab to set keyboard and mouse control properties for remote control sessions.

Keyboard

Option	Description
Remote keyboard (Send all keystrokes to Host)	Send all Guest computer keystrokes to the Host computer.
Local keyboard (Don't send special keystrokes)	Send the Guest computer keystrokes except Send Keystrokes keystroke combinations to the Host computer. Send Send Keystrokes keystroke combinations to the Guest computer.
No keyboard control	Send all the Guest computer keystrokes to the Guest computer.
Use Guest keyboard layout	If the Guest and Host computer keyboard layouts are different, some Guest computer keystrokes can come out wrong on the Host computer. To avoid this, select the Use Guest keyboard layout check box.
Don't transfer Host Num Lock, Scroll Lock, Insert and Caps Lock	With some display adapters, enabling these Host computer keyboard options may cause the Guest computer keyboard lights to flash. To avoid this, select the Don't transfer Host Num Lock, Scroll Lock, Insert and Caps Lock check box.

Mouse

Option	Description
Remote mouse (send all mouse events)	Send all Guest computer mouse events (clicks, drags and moves) to the Host computer.
Local mouse (Only send clicks and drags)	Send only Guest computer mouse clicks and drags to the Host computer to save transmission bandwidth.
No mouse control	Send no Guest computer mouse events to the Host .
Display Host mouse movements	Move the Guest computer mouse pointer in accordance with Host computer mouse pointer movements.

NOTE: To suppress **Guest** computer mouse pointer movements induced by the **Host** computer, press and hold the CTRL key.

Compression/Encryption tab

Use the Compression/Encryption tab to set data transmission properties.

Compression level

Netop Remote Control can compress transmitted data to speed up transmission across slow communication links. However, data compression takes time.

Option	Description
Automatic	Selects compression based on the properties of the applied communication profile. In most cases this provides the fastest transmission.
No compression	Typical selection for fast communication links.
Low	Typical selection for medium fast communication links.
High	Typical selection for slow communication links.

Host screen transfer

Option	Description
Transfer Host screen as commands	Typically faster, but with some Host computer display adapters some Host screen image details can be lost or corrupted.
Transfer Host screen as bitmap	Typically slower, but transfers Host screen image details correctly. When this option is selected the slider below becomes available. The slider has three options that range from better accuracy (Quality) to better performance (Speed). The middle option is a combination of the two. The default option is set to best quality. Here is how you use the slider: <ul style="list-style-type: none"> • Quality: More accuracy using an enhanced compression algorithm. • Center: Less accuracy but better performance using a TurboJPEG high compression ratio of 80. • Speed: Much less accuracy but much better performance using a TurboJPEG high compression ratio of 50.

NOTE: This section is disabled if you open the **Connection Properties** dialog box from the **Re-**

mote Control window.

Cache

Command mode **Host** screen transfer stores the screen image in cache memory and transfers only image changes. This saves transmission bandwidth and optimizes update speed.

The **Cache size** field displays the selected cache memory size. You can select Automatic and values from None to 10240 kb on the drop-down list.

Automatic selects the cache memory size based on the properties of the used communication profile. In most cases, this provides the optimum.

NOTE: This section is disabled if you open the **Connection Properties** dialog box from the **Remote Control** window.

Total Netop cache memory sharing and size is specified on the **Cache** tab in the **Program Options** window.

Preferred Encryption Type

The field displays the encryption type preferred by the **Guest**. You can select another encryption type on the drop-down list.

If the preferred encryption type is enabled on both **Guest** and **Host**, then it is applied.

If Netop 6.x/5.x Compatible is the preferred encryption type and not enabled on both **Guest** and **Host**, select a higher encryption level.

If another encryption type is preferred and this encryption type is not enabled on the **Host**, an encryption type that is enabled on both **Guest** and **Host** is applied.

If no common encryption type is enabled on **Guest** and **Host**, enable additional encryption types on the **Encryption** tab in the **Program Options** dialog box to achieve a match.

NOTE: The icon of the encryption type used in a remote control session are displayed on the status bar.

Desktop tab

Use the **Desktop** tab to specify transfer properties for **Host** computer desktop features.

Optimize screen transfer

Advanced Host computer desktop features slow down the Host screen transfer in command mode and are typically unimportant to the Guest user. Therefore, Netop Remote Control by default transfers the Host screen image without advanced desktop features.

However, you can change this and select which advanced desktop features to transfer.

Option	Description
Always	Always transfer without advanced desktop features.
Only when high compression	Transfer without advanced desktop features only with high compression, see Compression/Encryption tab.
Never	Never transfer without advanced desktop features.

Optimization parameters

Option	Description
Full optimization	Transfer without the desktop features listed below.
Custom optimization	<p>Select to enable the Custom options section below.</p> <p>You can then clear the selection of specific custom options to enable transfer of these advanced desktop features.</p> <p>Custom options:</p> <ul style="list-style-type: none"> • Disable wallpaper • Disable screen saver • Disable animation gimmicks • Disable full window drag • Disable Windows Aero <p>By default, all check boxes are selected.</p>

Record tab

Use the **Record** tab to enable remote control session recording.

Select the **Record remote control session** check box to record a remote control session.

Recording a remote control session creates a record on the **Recordings** tab. You can play back the recording from the **Recordings** tab.

If you select the Enforce recording check box on the **Program Options** window **Recording** tab, remote control sessions are recorded regardless of the selection on the **Record** tab.

NOTE: The **Record** section is disabled if you open the **Connection Properties** dialog box from the **Remote Control** window. Recording reduces the remote control session transfer speed.

Custom tab

Use the **Custom** tab to specify the properties of a custom application command.

Option	Description
Description	Specify a custom application name that is added as a command to the Host record context menu.
Command line	Specify the custom application command line (program file path, name and switches.) Click on the Browse button to open a program file and specify its path and name in the field.

NOTE: The **Custom** tab is only included if you open the **Connection Properties** dialog box from the **Phonebook** tab or the **History** tab.

5.1.9 Inventory

When you add an Inventory command to a script, the Inventory dialog box is displayed allowing you to specify what should happen to the inventory that is generated.

Option	Description
Inventory step	Select an Inventory step option in the drop-down list: <ul style="list-style-type: none"> • One Step: Generate, retrieve, copy and complete a Host computer inventory. • Generate: Generate inventory on the Host computer. • Retrieve: Save the generated inventory to the %TEMP%\si_out.xml file on the Host computer. NOTE: To make the retrieved inventory available for completion on the Guest computer, it must be copied by a file transfer Copy command from the Host computer to the Guest computer, typically to the %TEMP%\% directory. • Complete: Move a Host computer inventory file copied to the Guest computer to the inventory directory to enable displaying it on the Inventory tab. The inventory directory is located in the Netop configuration files directory, typically C:\Documents and Settings\<user name="">\Application Data\Netop\Netop Remote Control\Guest\inventor.</user>
Inventory file path	This field is enabled only if Complete is displayed in the Inventory step field. Specify the Guest computer path and name of the inventory file to be completed.

See also

[Script](#)

[Create and run a script](#)

[Generate a Host inventory](#)

5.1.10 Name Not Found

The **Name Not Found** dialog box advises you on how to overcome connect problems.

Here is some additional advice:

- Verify that communication can physically reach the **Host** computer:

If communicating across an IP network, execute this command in a Windows command prompt window:

```
PING <Host computer IP address>
```

This command sends four data packets to the specified IP address requesting replies. If positive replies are received, communication can physically reach the **Host** computer. If negative replies are received, check your network setup or consult your network/system administrator.

If communicating across a modem connection using Windows Modem, the setup of your modem in Windows may not satisfy Netop requirements. Try setting up your modem using Serial instead.

- In the **Host** window, on the **Names** tab, verify that the **Host** responds to the specified name or address with the selected communication profile. See Communication Profile Edit for further information about the characteristics of the communication device used by the selected communication profile.
- Try connecting to other **Hosts** starting with **Hosts** close to you. Try using other communication profiles and other **Host** names or addresses.
- Consult your network/system administrator.
- As a last resort, submit a support request to Netop Customer & Product Support.

5.1.11 Custom Inventory Items

Use the **Custom Inventory Items** dialog box to define additional inventory items that should be retrieved during an inventory scan.

Option	Description
Name	Enter a name for the custom inventory item.
Item type	Select an item type, for example Registry key, and fill in all fields for the selected item type as necessary.

The custom inventory item you created is displayed in the **Custom Inventory Items** pane in the

Advanced inventory option dialog box.

NOTE: The pane contents are stored in the Netop configuration file `InvCuItm.xml`, which is typically located here: `C:\Documents and Settings\\Application Data\Netop\Netop Remote Control\Guest`.

When you generate **Host** inventories, the inventories contain the custom inventory item that you defined.

See also

[Advanced inventory option](#)

[Program Options \(Inventory tab\)](#)

[Process Host computer inventory information](#)

5.1.12 Global Settings

Use the **Global Settings** dialog box to specify the script global settings that should apply as default settings for the subsequent script commands. The dialog box is displayed when you create a script.

To edit the global settings of a script, in the **Script** dialog box upper pane, select the **Global Settings** element and click on **Edit**.

General tab

Use the **General** tab to specify the global file transfer direction.

Option	Description
From	Select Guest or Host in the drop-down list. Displays the global source Netop module name.
To	Displays the receiving Netop module, i.e. the Netop module name that has not been selected in the From drop-down list. The field cannot be edited.

Transfer tab

Use the **Transfer** tab to specify global file transfer settings.

Option	Description
Use delta file transfer	Select this check box to compare source files with destination files and transfer only the difference between source files and destination files. This saves transmission bandwidth.
Enable crash recovery	Select this check box to transfer files in a way so that they can be re-

	covered after a computer or network crash during transfer.
--	--

Overwrite/Delete tab

Use the **Overwrite/Delete** tab to specify global overwrite and delete settings.

Option	Description
Allow overwriting/deleting existing files/folders	Select this check box to allow overwriting and deleting files and folders on the destination computer.
Allow overwriting/deleting system files	Select this check box to allow overwriting and deleting system files on the destination computer.
Allow overwriting/deleting read-only files	Select this check box to allow overwriting and deleting read-only files on the destination computer.
Allow overwriting/deleting hidden files	Select this check box to allow overwriting and deleting hidden files on the destination computer.

Advanced tab

Use the **Advanced** tab to specify global error handling and the log file settings.

Error Handling

Option	Description
On communication error	<p>Specifies the action in case of a communication error.</p> <p>Select an option in the drop-down list:</p> <ul style="list-style-type: none"> • Exit: End the script. • Next Host: Proceed to the next Host specified in the script. • Retry 1 time: Retry the failed command once. • Retry 2 times: Retry the failed command twice. • etc.
On transfer error	<p>Specifies the action in case of a file transfer error.</p> <p>Select an option in the drop-down list:</p> <ul style="list-style-type: none"> • Exit: End the script. • Next Host: Proceed to the next Host specified in the script. • Next File: Proceed to the next file specified in the script. • Retry 1 time: Retry the failed command once. • Retry 2 times: Retry the failed command twice. • etc.

Log File

Option	Description
Generate log file	Select this check box to generate a log file when running the script.
Append if log exists	Select this check box to append the log to an existing log file with the specified name. Clear the selection to overwrite. The field below the check box specifies the log file path and name (default: SCRIPT.LOG). Click on the Browse button to open a different log file. If no path is specified, the log file is located in the Netop configuration files folder, typically C:\Documents and Settings\ <user name="">\Application Data\Netop\Netop Remote Control\Guest\.</user>

Option	Description
Restart script when finished	Select this check box to restart the script at script end.
Close Guest when finished	Select this check box to unload the Guest at script end.

See also

- [Script](#)
- [Create and run a script](#)

5.1.13 IP Broadcast List

For TCP/IP broadcast communication to reach computers on remote network segments when Netop Name Management is not used, make sure that the IP addresses or DNS names are listed in the IP Broadcast List. For further information about Netop Name Management, see the Administrator's Guide.

Click on the **Add** button to open a dialog box allowing you to add a DNS name or IP addresses.

Specify an IP address, for example 192.168.102.57, an IP address range, for example 192.168.102.20 -192.168.102.30, or a DNS name, for example MAIL_SVR, to add it to the IP Broadcast List, and click on **OK**.

NOTE: Specifying an IP address range makes each broadcast send a number of data packets corresponding to the number of IP addresses in the range. To avoid excessive network traffic, do not specify larger IP address ranges than justified.

Select the **Disable local subnet broadcast** check box to disable broadcast communication to local network segment computers.

See also

[Communication Profile Edit](#)

5.1.14 Log Setup

Log Setup tab

Use the **Log Setup** tab to specify where to log.

Log events

Option	Description
Log locally	Select this check box to log Netop events in a log file on the computer.
Log on Netop server	Select this check box to log Netop events in the database log of a central Netop Security Server.
Log to Windows event log	Select this check box to log Netop events in the Windows event log of the computer and/or of another Windows NT/2000/XP/2003/2008/Vista/7 computer.
Log using SNMP traps	Select this check box to log Netop events by sending SNMP messages to a management information system.
Custom Host Name for all log events	<p>Select this check box to identify logged events by a customized Host name.</p> <p>The left field specifies the customized Host name composed from components and keyboard characters on the drop-down list to the right. Select a component on the drop-down list to add it in the left field.</p> <p>The following components are available:</p> <ul style="list-style-type: none"> • %A: IP/MAC address • %I: Host ID • %C: Computer name • %L: Windows logon user name
Custom Guest name for Connection and Session log events	<p>Select this check box to identify Guests engaged in Connection and Session log events by a customized name.</p> <p>The left field specifies the customized Guest name composed</p>

from components and keyboard characters on the drop-down list to the right. Select a component from the drop-down list to add it in the left field.

The following components are available:

- %A: IP/MAC address
- %U: Authenticated user name
- %I: Guest ID
- %C: Computer name
- %L: Windows logon user name

Example of a custom Host and Guest name local Netop log

```
20080903,14:10,Host1+User1,0,00000,00000,HCON +,
20080903,14:10,Host1+User1,1,00000,00000,HSES +,User-
2@192.168.1.2
20080903,14:10,Host1+User1,2,00000,00000,HSESRC +,User-
2@192.168.1.2
20080903,14:10,Host1+User1,3,00000,00000,HSESFXFER
+,User2@192.168.1.2
20080903,14:10,Host1+User1,4,00000,00000,HSESCHAT
+,User2@192.168.1.2
20080903,14:10,Host1+User1,5,00000,00000,HSESAUDIO
+,User2@192.168.1.2
20080903,14:10,Host1+User1,6,00000,00000,HSESAUDIO-
,User2@192.168.1.2
20080903,14:10,Host1+User1,7,00000,00000,HSESCHAT
,User2@192.168.1.2
20080903,14:11,Host1+User1,8,00000,00000,HSESFXFER-
,User2@192.168.1.2
20080903,14:11,Host1+User1,9,00000,00000,HSESRC -,User-
2@192.168.1.2
20080903,14:11,Host1+User1,10,00000,00000,HSES -,User-
2@192.168.1.2
```

The Host name was customized as %C+%L. The Guest name was customized as %U+%A.

The Host was started and the Guest started a remote control session, a file transfer session, a chat session and an audio-

	video chat session and ended sessions in reverse order.
--	---

Netop Security Server has an additional check box:

Act as log server: Select this check box to enable logging other Netop modules' Netop events in the security database Netop Log.

Netop Local tab

Use the **Netop Local** tab to specify which Netop events should be logged and the local Netop log file.

Select Events to view in list

Option	Description
View all Events	Display all available events in the Events to log list.
View Selected	Select event types to display in the Events to log list: <ul style="list-style-type: none"> • Connection • Session • Action • Security • Configuration

Events to log

In the Events to log list, select the events you wish to log.

See [Available Netop log event codes and arguments - Guest](#).

Log File

This section is only enabled if the Log locally check box has been selected on the Log Setup tab.

Option	Description
Log file name	Displays the (path and) name of the log file (default: NETOP.LOG). If no path is specified, the log file is located in the Netop configuration files folder, typically C:\Documents and Settings\ <user name="">\Application Data\Netop\Netop Remote Control\<module name>.<="" td=""> </module></user>
Write to disk for each log entry	Select this check box to write each Netop event to the local Netop log file immediately. Clear the check box to write Netop events to the local Netop log file when the Netop module is unloaded, which consumes less processor capacity.

NOTE: A new local Netop log file that is created when the Netop module is loaded overwrites an old local Netop log file with the same path and file name.

Netop Server tab

Use the Netop Server tab to specify which Netop events should be logged and the Host ID of the logging server.

Select Events to view in list

Option	Description
View all Events	Display all available events in the Events to log list.
View Selected	Select event types to display in the Events to log list: <ul style="list-style-type: none"> • Connection • Session • Action • Security • Configuration

Events to log

In the **Events to log** list, select the events you wish to log.

See [Available Netop log event codes and arguments - Guest](#).

Host ID for Log Server

This section is only enabled if the Log on Netop server check box has been selected on the Log Setup tab.

Specify the Host ID of the Netop server on which Netop events should be logged. Click on the **Browse** button to browse the network for available logging Netop servers.

NOTE: If the Use Netop Security Server option (in Guest Access Security) is selected on a Host or extended Host, leave the Host ID for Log Server field empty to log in the database log of the specified security server.

Windows Event Log tab

Use the Windows Event Log tab to specify which Netop events should be logged and Windows event logs.

Select Events to view in list

Option	Description
View all Events	Display all available events in the Events to log list.
View Selected	Select event types to display in the Events to log list: <ul style="list-style-type: none"> • Connection • Session • Action • Security • Configuration

Events to log

In the Events to log list, select the events you wish to log.

See [Available Netop log event codes and arguments - Guest](#).

Use Windows event log

This section is enabled only if the Log to Windows event log check box is selected on the **Log Setup** tab.

Option	Description
Local	Select this check box to log Netop events in the Windows event log of the computer.
Remote	Select this check box to log Netop events in the Windows event log of a remote Windows NT/2000/XP/2003/2008/Vista/7 computer. Specify the Windows name of the remote computer.

SNMP Traps tab

Use the SNMP Traps tab to specify which Netop events to log in a management information system.

Select Events to view in list

Option	Description
View all Events	Display all available events in the Events to log list.
View Selected	Select event types to display in the Events to log list: <ul style="list-style-type: none"> • Connection • Session • Action • Security • Configuration

Events to log

In the **Events to log** list, select the events you wish to log.

See [Available Netop log event codes and arguments - Guest](#).

If the **Log using SNMP Trapsbox** is selected on the **Log Setup** tab, a Simple Network Management Protocol (SNMP) message is sent when a selected Netop event occurs.

NOTE: Netop SNMP events are defined in the `danware.mib` file located in the folder where the Netop module is installed.

5.1.14.1 Available Netop log event codes and arguments - Guest

The **Guest** can log the following Netop log events:

Connection

Event Name	Event Code	Arguments
Con: Call Host	GCONCALL	Host name
Con: Disconnect Host	GCONHNGUP	Host name
Con: Connection lost	*CONLOST	Host name
Con: User authenticated	GCONUSER	(none)
Ses: Remote control started	GSESRC +	Host name

Session

Event Name	Event Code	Arguments
Ses: Remote control stopped	GSESRC -	Host name
Ses: File transfer started	GSESFXFER+	(none)
Ses: File transfer stopped	GSESFXFER-	(none)
Ses: Chat started	GSESCHAT +	(none)
Ses: Chat stopped	GSESCHAT -	(none)
Ses: Audio started	GSESAUDIO+	(none)
Ses: Audio stopped	GSESAUDIO-	(none)
Ses: Remote Management started	GSESRM +	Host name
Ses: Remote Management stopped	GSESRM -	Host name

Action

Event Name	Event Code	Arguments
Act: Help service start	GACTHLPSV+	(none)
Act: Help service stop	GACTHLPSV-	(none)
Act: Help request received	GACTHLPRQ+	Host name
Act: Help request canceled	GACTHLPRQ-	Host name
Act: File received	*ACTFILE +	File path and name
Act: File Sent	*ACTFILE -	File path and name
Act: Host Rebooted	*ACTBOOT	Host name
Act: Session recording started	GACTREC +	Recording file path and name
Act: Session recording stopped	GACTREC -	Recording file path and name
Act: Windows event logging failed	*ACTWIN !	(none)
Act: SNMP trapping failed	*ACTSNMP !	(none)
Act: Received Clipboard	*ACTCLPB +	(none)
Act: Sent Clipboard	*ACTCLPB -	(none)
Act: Received Print Job	*ACTPRINT+	(none)
Act: Sent Print Job	*ACTPRINT-	(none)
Act: Communication Profile Started	GACTCOMPR+	Communication profile name
Act: Communication Profile Stopped	GACTCOMPR-	[Communication profile name]
Act: Inventory received	GACTINV	Host name
Act: Message sent	GACTMSG	Host name

Security

Event Name	Event Code	Arguments
Sec: Password rejected	*SECPW !	Host name
Sec: Confirm access granted	*SECCA (10 characters, 4 blank spaces at the end)	Host name
Sec: Confirm access denied	*SECCA !	Host name
Sec: Security Server logon	GSECACSRV+	Logon name
Sec: Security Server logoff	GSECACSRV-	(none)

Configuration

Event Name	Event Code	Arguments
Cfg: Help service name defined	GCFGHLPSV+	Help service name
Cfg: Help service name deleted	GCFGHLPSV-	Help service name
Cfg: Local logging turned on	*CFGLLOC +	Log file name
Cfg: Local logging turned off	*CFGLLOC -	Log file name
Cfg: Local logging filename changed	*CFGFILE*	New log file name
Cfg: Server logging turned on	*CFGLSRV +	Log server name
Cfg: Server logging turned off	*CFGLSRV -	Log server name
Cfg: Windows event logging turned on	*CFGLWIN +	If remote: computer name
Cfg: Windows event logging turned off	*CFGLWIN -	If remote: computer name
Cfg: Sending SNMP traps turned on	*CFGLSNMP+	(none)
Cfg: Sending SNMP traps turned off	*CFGLSNMP-	(none)
Cfg: Security Server password changed	GCFGACPW *	Netop Guest ID
Cfg: Web update check	*CFGWUCHK	Old build, new build, [timeout error]
Cfg: Web update download	*CFGWUDL	File name, [timeout error]
Cfg: Web update install	*CFGWUINST	(none)
Cfg: Web update success	*CFGWU *	Old build, new build
Cfg: Web update failed	*CFGWU !	Old build, error message

5.1.14.2 Available Netop log event codes and arguments - Host

The **Host** or extended **Host** can log the following Netop log events:

Connection

Event Name	Event Code	Arguments
Con: Host started	HCON +	(none)
Con: Host stopped	HCON -	(none)
Con: Callback	HCONCALLB	Callback number
Con: Connection lost	*CONLOST	(none)

Con: Name Server started	HCONNNS +	(none)
Con: Name Server stopped	HCONNNS -	(none)
Con: Security Server started	HCONNSS +	(none)
Con: Security Server stopped	HCONNSS -	(none)
Con: Gateway started	HCONGW +	(none)
Con: Gateway stopped	HCONGW -	(none)

Session

Event Name	Event Code	Arguments
Ses: Session started	HSES +	Guest name
Ses: Session stopped	HSES -	Guest name
Ses: Remote control started	HSESRC +	Guest name
Ses: Remote control stopped	SESRC -	Guest name
Ses: File transfer started	HSESFXFER+	Guest name
Ses: File transfer stopped	HSESFXFER-	Guest name
Ses: Chat started	HSESCHAT +	Guest name
Ses: Chat stopped	HSESCHAT -	Guest name
Ses: Audio started	HSESAUDIO+	Guest name
Ses: Audio stopped	HSESAUDIO-	Guest name
Ses: Remote Management started	HSESRM +	Guest name
Ses: Remote Management stopped	HSESRM -	Guest name
Ses: Maintenance password for confirm access wrong. Guest access denied	SESACCTR!	Guest name
Ses: Maintenance password for confirm access ok. Guest allowed access	SESACCTR	Guest name

Action

Event Name	Event Code	Arguments
Act: Help request sent	HACTHLPRQ+	Help service name, problem description
Act: Help request canceled	HACTHLPRQ-	(none)
Act: File received	*ACTFILE +	File path and name
Act: File sent	*ACTFILE -	File path and name
Act: Host reboot	*ACTBOOT	(none)
Act: Run Program	HACTRUN	Program name

Act: Execute Command	HACTEXE	Command name
Act: Windows event logging failed	*ACTWIN !	(none)
Act: SNMP trapping failed	*ACTSNMP !	(none)
Act: Received clipboard	*ACTCLPB +	(none)
Act: Sent clipboard	*ACTCLPB -	(none)
Act: Received print job	*ACTPRINT +	(none)
Act: Sent print job	*ACTPRINT -	(none)
Act: Keyboard and mouse assigned	HACTKBDMS+	Guest name
Act: Keyboard and mouse revoked	HACTKBDMS-	Guest name
Act: Keyboard locked	HACTKBD -	(none)
Act: Keyboard unlocked	HACTKBD +	(none)
Act: Screen blanked	HACTSCR -	(none)
Act: Screen unblanked	HACTSCR +	(none)
Act: Host user logged off	HACTLOFF	(none)
Act: Gateway logon	HACTGW +	Connecting module name
Act: Inventory sent	HACTINV	Guest name
Act: Message received	HACTMSG	Guest name

Security

Event Name	Event Code	Arguments
Sec: Individual security enabled or changed	HSECINDIV+	Guest access method
Sec: Individual security disabled	HSECINDIV-	Guest access method
Sec: Security role added	HSECROLE +	Security role name
Sec: Security role deleted	HSECROLE -	Security role name
Sec: Security role changed	HSECROLE *	Security role name
Sec: Guest added to role	HSECGUEST+	Guest name
Sec: Guest deleted from role	HSECGUEST-	Guest name
Sec: Guest changed in role	HSECGUEST*	Guest name
Sec: Password enabled	HSECPW +	If individual: Guest name
Sec: Password disabled	HSECPW -	If individual: Guest name
Sec: Password changed	HSECPW *	If individual: Guest name
Sec: Callback enabled (default only)	HSECCALLB+	(none)
Sec: Callback disabled (default only)	HSECCALLB-	(none)

Sec: Callback changed (default only)	HSECCALLB*	(none)
Sec: Confirm access enabled	HSECCA +	If individual: security role name
Sec: Confirm access disabled	HSECCA -	If individual: security role name
Sec: Password rejected	*SECPW !	Guest name
Sec: Confirm access granted	*SECCA (10 characters, 4 blank spaces at the end)	(none)
Sec: Confirm access denied	*SECCA !	(none)
Sec: Illegal password limit reached	HSECPWLIM!	(none)
Sec: Timeout limit exceeded	HSECTMOUT	AC (inactivity), AU (authentication) or CA (confirm access)

Configuration

Event Name	Event Code	Arguments
Cfg: Local logging started	*CFGLLOC +	Log file name
Cfg: Local logging stopped	*CFGLLOC -	Log file name
Cfg: Local logging filename changed	*CFGLFILE*	New log file name
Cfg: Server logging started	*CFGLSRV +	Log server name
Cfg: Server logging stopped	*CFGLSRV -	Log server name
Cfg: Windows event logging started	CFGLWIN +	If remote: computer name
Cfg: Windows event logging stopped	*CFGLWIN -	If remote: computer name
Cfg: Sending SNMP traps started	*CFGLSNMP+	(none)
Cfg: Sending SNMP traps stopped	*CFGLSNMP-	(none)
Cfg: Option change: Start at load	HCFGOWAIT*	ON/OFF
Cfg: Option change: Load with OS	HCFGOLOAD*	ON/OFF
Cfg: Option change: Minimize at startup	HCFGOMIST*	ON/OFF
Cfg: Option change: Stealth mode	HCFGOSTLT*	ON/OFF
Cfg: Option change: Minimize on connection	HCFGOMICO*	ON/OFF
Cfg: Option change: On top	HCFGOTOP *	ON/OFF
Cfg: Option change: Show file	HCFGOSFX *	ON/OFF

transfer		
Cfg: Option change: Send keep alive	HCFGGOALIV*	ON/OFF
Cfg: Option selected: Boot after disconnect	HCFGGOBOOT+	(none)
Cfg: Option selected: Logoff after disconnect	HCFGGOLOGO+	(none)
Cfg: Option selected: Lock after disconnect	HCFGGOLOCK+	(none)
Cfg: Option selected: Nothing after disconnect	HCFGGONOTH+	(none)
Cfg: Option change: Naming method	HCFGGONAME*	(none)
Cfg: Option change: Public Host name	HCFGGOPUBN*	ON/OFF
Cfg: Option change: Enable user name	HCFGGOUSRN*	ON/OFF
Cfg: Option change: Connection notification	HCFGGONOTI*	(none)
Cfg: Option change: Help Request description	HCFGGOHRD *	(none)
Cfg: Option change: Help Request provider	HCFGGOHRP *	(none)
Cfg: Option change: Help Request communication	HCFGGOHRC *	(none)
Cfg: Option change: Help Request phone/IP	HCFGGOHRPI*	(none)
Cfg: Option change: Help Request show icon	HCFGGOHRSI*	ON/OFF
Cfg: Option change: Audio full duplex	HCFGGOAUFD*	ON/OFF
Cfg: Option change: Audio silence level	HCFGGOAUSL *	(none)
Cfg: Option change: Audio line hold	HCFGGOAULH*	(none)
Cfg: Option change: Name space ID	HCFGGONSID*	(none)
Cfg: Maintenance requiry changed	HCFGGMRQG*	(none)

for Guest		
Cfg: Maintenance requiry changed for Gateway	HCFGMRQGW*	(none)
Cfg: Maintenance requiry changed for other	HCFGMRQO *	(none)
Cfg: Maintenance requiry changed for exit/stop	HCFGMRQEX*	(none)
Cfg: Protect files changed	HCFGPROTS*	(none)
Cfg: Maintenance password changed	HCFGMTPW *	(none)
Cfg: Guest access allow to changed (default only)	HCFGGALLW*	(none)
Cfg: MAC/IP address list changed	HCFGMACIP*	(none)
Cfg: File transfer disable changed	HCFGFX *	(none)
Cfg: Security Server group ID changed	HCFGSSG *	(none)
Cfg: Web update check	*CFGWUCHK	Old build, new build, [timeout error]
Cfg: Web update download	*CFGWUDL	File name, [timeout error]
Cfg: Web update install	*CFGWUINST	(none)
Cfg: Web update success	*CFGWU *	Old build, new build
Cfg: Web update failed	*CFGWU !	Old build, error message
Cfg: Maintenance password for confirm access enabled	HCFGACCTR+	(none)
Cfg: Maintenance password for confirm access disabled	HCFGACCTR-	(none)

Netop Gateway can log these Netop log special Gateway events:

Event Name	Event Code	Arguments
GW: Gateway access allowed	HGW ACCES+	(none)
GW: Gateway callback	HGW CALLB	Callback number
GW: Gateway callback changed (default only)	HGW CALLB*	(none)
GW: Gateway callback disabled (default only)	HGW CALLB-	(none)
GW: Gateway callback enabled (default only)	HGW CALLB+	(none)

GW: Gateway group defined	HGW GROUP+	Security role name
GW: Gateway group deleted	HGW GROUP-	Security role name
GW: Gateway Guest added	HGW GUEST+	Guest name
GW: Gateway Guest changed	HGW GUEST*	Guest name
GW: Gateway Guest deleted	HGW GUEST-	Guest name
GW: Gateway individual security disabled	HGW INSEC-	(none)
GW: Gateway individual security enabled (or changed)	HGW INSEC+	(none)
GW: Gateway NSS GID changed	HGW SSGID*	(none)
GW: Gateway password changed (default only)	HGW PW *	(none)
GW: Gateway password disabled (default only)	HGW PW -	(none)
GW: Gateway password enabled (default only)	HGW PW +	(none)
GW: Gateway password rejected	*SECGWPW !	Connecting module name

5.1.15 Netop File Manager Options

Use the **Options** dialog box to set up how file transfer should work.

You can set up synchronization options, general transfer options, options for display of confirmation dialog boxes in relation to deleting/overwriting files during file transfer, **File Manager** layout options, and options for logging during file transfer.

Transfer tab

Synchronize

Option	Description
Transfer only if file exists	Select this check box to synchronize files only if they exist in the unselected pane.
Transfer only one way	Select this check box to synchronize files only from the selected pane to the unselected pane.

General Transfer

Option	Description
Include subfolders	Select this check box to transfer also the contents of subfolders of se-

	lected folders.
Use delta file transfer	Select this check box to compare source files with corresponding destination files and transfer only differences between source and destination files. This saves transmission bandwidth.
Enable crash recovery	Select this check box to transfer files so that they can be recovered after a computer or network crash during file transfer.
Close dialog when finished	Select this check box to close the Transfer Status window when a file transfer is finished.
End session when finished	Select this check box to end the file transfer session when a file transfer is finished.

Confirmation tab

Confirm when...

Option	Description
Delete non-empty folders	Select this check box to display a confirmation dialog box if you are about to delete a folder containing folders or files. The confirmation dialog box allows you the following choices with regard to the deletion: <ul style="list-style-type: none"> • Skip: Click on this button to skip deleting the specified folder. • Delete: Click on this button to delete the specified folder. • Advanced: Click on this button to change your delete confirmation selections for this file transfer only. • Cancel: Click on this button to cancel the file transfer at this point. You cannot undo executed file transfer actions.
Overwriting/deleting files	Select this check box to display a confirmation dialog box if you are about to overwrite or delete files. The confirmation dialog box allows you the following choices with regard to the overwriting/deletion: <ul style="list-style-type: none"> • Skip: Click on this button to skip overwriting the specified file. • Overwrite: Click on this button to overwrite the specified file. • Advanced: Click on this button to change your overwriting confirmation selections for this file transfer only.
Overwriting/deleting read-only files	Select this check box to display a confirmation dialog box if you are about to overwrite/delete read-only files.
Overwriting/deleting hidden files	Select this check box to display a confirmation dialog box if you are about to overwrite/delete hidden files.

den files	about to overwrite/delete hidden files.
Overwriting/deleting system files	Select this check box to display a confirmation dialog box if you are about to overwrite/delete system files.
Drag and drop (copying files with the mouse)	Select this check box to display a confirmation dialog box before executing a drag and drop file transfer.

Layout tab

Screen

Option	Description
Show toolbar	Select this check box to display the toolbar of the Netop File Manager window.
Show status bar	Select this check box to display a status bar at the bottom of the two panes in the Netop File Manager window.
Save session path at exit	Select this check box to display the same pane contents when starting a file transfer session with the same Host the next time. Uncheck to always display the system drive contents when starting a file transfer session.

Keyboard

Option	Description
Use system hotkey layout	Select this option to use the operating system hotkey layout, see the table below.
Use Netop hotkey layout	Select this option to use the Netop hotkey layout, see the table below.

Function	Windows hotkey	Netop hotkey
Copy Files		F3
Move Files		F6
New Folder		F7
Delete	DELETE	F8
Rename	F2	
Close	ALT+F4	F10
Properties	ALT+ENTER	SHIFT+F1
Select All	CTRL+A	
Select by		+
Deselect by		-
Invert selection		*

Arrange Icons By Name		CTRL+F3
Arrange Icons By Type		CTRL+F4
Arrange Icons By Size		CTRL+F6
Arrange Icons By Date		CTRL+F5
Refresh	F5	CTRL+R
Select the left record panel		ALT+F1
Select the right record panel		ALT+F2
Help	F1	F1

Icons

Option	Description
Local associated and Host 'exe' icons	Display file icons in the Netop File Manager window panes according to Guest file associations, but display Host exe file icons according to Host file associations.
Local associated icons	Display file icons in the Netop File Manager window panes according to Guest file associations. This saves transmission bandwidth.
Default icons	Display the same default icon for all files in the Netop File Manager window panes. This saves transmission bandwidth and processor capacity.

Logging tab

Option	Description
Generate log file	Select this check box to generate a file transfer log file when ending a file transfer session.
Append if log file exists	Select this check box to append new log entries to an existing log file. If you do not select it, any existing log file is overwritten.
Filename	This field specifies the log file (path and) name. The default name is NFM.LOG. The file is located in the Netop configuration files folder, typically C:\Documents and Settings\ <user name="">\Application Data\Netop\Netop Remote Control\Guest. Click on the Browse button to specify another log file path and</user>

	name.
--	-------

See also

[Transfer files](#)

5.1.16 Modem

Use the **Modem** dialog box to manage the modem database.

NOTE: The modem database is stored in the Netop configuration file `modems.ndb`, which is typically located in the directory `C:\Documents and Settings\\Application Data\Netop\Netop Remote Control\.`

In the **Modem List** the first `_Modem Database YYYYDDD` record specifies the modem database update year and day number. You can download and install the newest available update from the Netop KnowledgeBase, see the Download Updates subsection.

NOTE: Downloading and installing `modems.ndb` overwrites your current `modems.ndb`.

Other records represent modem configurations created by Netop Support or added by a user. You can create, edit and delete modem configurations using the buttons at the bottom of the dialog box.

To base a new modem configuration on an available modem configuration, select the modem configuration in the pane before clicking on the **New** button.

See also

[Modem Configuration](#)

5.1.17 Modem Configuration

Use the **Modem Configuration** dialog box to create or edit a modem configuration in the modem database.

With some modem configurations, some or all fields are disabled to protect the original modem configuration. If you select a modem configuration in the **Modem** dialog box and click on **New**, the properties of the selected modem configuration are displayed in the **Modem Configuration** dialog box with all fields enabled.

The **Name** field contains the modem configuration name, which must be unique within the modem database. You can edit the field contents.

Modem command strings

These fields specify the modem AT command strings. Consult with your modem manual or the modem manufacturer website to find the AT command strings required by your modem.

Max data rate

In the Max data rate drop-down list, select a data rate applicable to your modem and the modem you want to connect to.

Settings

Option	Description
RTS/CTS Flow control	Select this check box to use Return To Send/Clear To Send flow control.
Ignore carrier signal	Normally, no carrier signal indicates an error. However, in some situations there may not be any carrier signal, without this being an error. Select this check box to not wait for a carrier signal.

See also

[Modem](#)

5.1.18 Novell Network Numbers

Unless a network list is created, the IPX communication reaches only the Netop modules on the local network. You can extend the communication to remote networks.

In the **Novell Network Numbers** dialog box you can add, edit, and delete network numbers using the buttons on the right side of the network list.

The pane displays the 8-digit hexadecimal network numbers of the selected remote networks.

See also

[Communication Profile Edit](#)

5.1.19 Program Options

Layout tab

Use the **Layout** tab to specify layout options for the **Guest** window.

Enable

Option	Description
Tool bar	Clear the selection of this check box to remove the toolbar.
Status line	Clear the selection of this check box to remove the status bar.
Menu hints	Clear the selection of this check box to disable the display of menu command and toolbar button hints in the status bar.
Add Guest icon to tray	Clear the selection of this check box to display no Netop Guest icon in the notification area in the lower right screen corner when the Guest is loaded.
Hide Guest from taskbar when minimized	This option is only available if the Add Guest icon to tray check box is selected. Clear the selection of this check box to display the minimized Guest as an icon in the taskbar at the bottom of the screen. If selected, the minimized Guest is displayed only as a Netop Guest icon in the notification area in the lower right corner of the screen.
Save Guest minimize state on exit	Select this check box to load the Guest minimized if minimized when the Guest last unloaded.
Stealth mode (hide Guest when started)	Select this check box to load the Guest hidden to the computer user. To uncover the Guest when loaded in stealth mode, execute showgst.exe , which is located in the directory in which the Guest was installed.

Use the **Menu and Toolbar Theme** list to select color theme for the menu and toolbar.

Tab layout

Use the **Tab layout** option to enable/disable tab panel tabs and rearrange the order of the tabs.

The pane contains a list of available tab panel tab names.

Remove the selection of a check box to remove the tab in question from the tab panel.

The order of the tab names in the pane from top to bottom controls the order of the tab panel from left to right. Select a tab name and click on one of the **Up/Down** buttons to move it.

NOTE: For the changes to take effect, make sure to restart the **Guest**.

General tab

Use the **General** tab to specify general connect options.

Option	Description	
Host session default mode	Select a session to start when connecting to a Host . Remote control is the default session.	
Inactivity	In the Inactivity timeout field, specify a number of minutes after which to disconnect if there has been no Guest user keyboard or mouse activity within the specified number of minutes (default: 0, range 0-999).	
Keep Alive	Select the Send keep alive message check box to send a data packet at intervals while connected to alert the Guest if the connection is lost. NOTE: To maintain an ISDN (CAPI) connection during short periods of inactivity, select the Short-hold mode check box in the Edit dialog box for the ISDN (CAPI) communication profile.	
Confirm when	Select the Exiting Guest while connected check box to display a warning if you attempt to unload the Guest while being connected to a Host. You are prompted to confirm if you want to unload the Guest anyway.	
Connection	Option	Description
	Connection attempts	Specify a number of connection attempts in the range 1-999 that the Guest should automatically make to connect to a Host.
	Auto reconnect	In the list, select the reconnect option that should apply if a connection is lost: <ul style="list-style-type: none"> • Never: Never reconnect. • Abnormal disconnect only: Reconnect only if the connection is lost by an abnormal event. • Host disconnect only: Reconnect only if the Host disconnected. • Always: Always reconnect.
Netop Portal settings	Certificate...	You can modify the following options: <ul style="list-style-type: none"> • Connection allowed when using an invalid certificate • Display invalid certificate warning (enabled by default)
	Proxy...	By default, no proxy is used when initializing the Netop Portal communication profile. This setting can be changed, to either attempt to detect and use the current proxy settings of the system. Available options: <ul style="list-style-type: none"> • no proxy • use system proxy settings (enabled by default); when enabled, it automatically detects the proxy configuration of the system from the Internet Options

		<ul style="list-style-type: none"> • use custom proxy settings <p>NOTE: It is necessary that you specify at least the address (IP/DNS name) and port.</p>
--	--	---

Cache tab

Use the **Cache** tab to specify disk cache options for the remote control screen image.

When the **Guest** remote controls a **Host** in command mode, the **Guest** stores the **Host** screen image in disk cache memory to transfer only image changes. This speeds up **Host** screen image update and saves transmission bandwidth.

Host screen command transfer disk cache

Option	Description
Use separate cache file for each Host	Select this option to reserve a disk cache section for each connected and disconnected Host . If you connect to many different Hosts, a large total disk cache size is required to achieve high update and reconnect speed.
Use shared cache file for all Hosts	Select this option to share the available disk cache among connected and disconnected Hosts . Total disk cache size demand is typically lower.
Don't save cache between sessions	Select this option to share the available disk cache only among connected Hosts . Total disk cache demand is lowest, but reconnects are slower.
Limit total disk cache size to	In this field, specify a disk cache size in the range 200 - 64000 (default: 10000). The number should typically be larger than default if you regularly run command mode remote control sessions with many different Hosts .

Logon tab

Use the **Logon** tab to specify **Guest** logon and name options.

Guest ID

The contents of the **Guest ID** field specify the name by which the **Guest** identifies itself when communicating (default: computer name).

You can edit the field content.

If the field is empty, the **Guest** identifies itself by its computer address, typically IP address or network card MAC address.

NOTE: If the **Guest** runs on a network computer, we recommend naming it by its computer name. If the **Guest** runs on a terminal server client, we recommend naming it by its user logon name. See the [Administrator's Guide](#), Advanced Tools, Netop Naming in a TSE.

Authentication

Select the **Cache logon passwords** check box to store the most recently used logon credentials in cache memory and apply them when connecting.

Cached logon credentials are lost when the **Guest** is unloaded.

Access Server 6.x/5.x

Option	Description
Use Access Server on Guest side	Select this check box to enable Guest side authentication with Hosts that are Guest side authentication enabled on an older version of Netop Access Server. NOTE: Netop Security Server (version 7+ only) does not support Guest side authentication.
Ignore if access to Host cannot be authenticated	Select this check box to ignore Guest side authentication with Hosts that are not Guest side authentication enabled on a Netop Access Server.

Host Name tab

Use the **Host Name** tab to specify **Host** name and **Netop Name Server** name space ID options.

Default Host name qualifier

Netop interprets a name specified in the Quick Connect tab, in the Host section Name field as a certain type of name according to this default Host name qualifier or a prefixed Host name qualifier (shown in parentheses below).

Option	Description
Host ID (H::)	Interprets a Host name without a prefix as a Host ID.
User name (U::)	Interprets a Host name without a prefix as a user name.
DNS name (DNS::)	Interprets a Host name without a prefix as a Domain Name Server name.
LDAP name (LDAP::)	Interprets a Host name without a prefix as a directory services user at-

tribute value. See [Directory Services](#) tab.

Duplicate names

If connecting by a networking communication device, multiple Hosts may respond by the same name, for instance if the same user is logged on to multiple computers. By default, the **Guest** connects to the first responding **Host**.

Select the **Check for duplicate names before connecting** check box to wait a few seconds for Host responses and display a **Multiple Host Names found** window if multiple Hosts respond. The window prompts you to select a **Host**.

Netop Name Server

To connect by name resolution using Netop Name Server, use a communication profile that uses the TCP/IP communication device. In the **Advanced TCP/IP Configuration** dialog box, select the **Use Netop Name Server** check box and specify the resolving Netop Name Server addresses. Make sure to specify the same Name Space ID as the Netop modules that you want to connect to.

In the **Name Space ID** field specify the Name Space ID specified by the Netop modules that you want to connect to using Netop Name Server (default: PUBLIC).

See also

[Communication Profile Edit Administrator's Guide](#), Netop Name Management.

Directory Services tab

Use the Directory Services tab to specify directory services to enable the Guest to connect to and browse for Hosts using the LDAP:: Host name qualifier.

General

Option	Description
Directory Server	Specify the directory server IP address or DNS name.
Port	Specify the port through which to connect to the directory server (default: 389, the Lightweight Directory Access Protocol (LDAP) port). Select the Use secure connection check box to connect to the directory server by a secure connection. The LDAP secure connection port number is 636.
Base DN	Specify the directory services distinguished name from which a search

	should start.
--	---------------

Credentials tab

Specify the credentials by which the **Guest** should log on to the directory server. The credentials determine the user rights by which directory services information is available.

Option	Description
Anonymous bind	Select this check box to search the directory service with anonymous user rights. Clear the selection to enable the fields below.
User DN	Specify a directory service user distinguished name to search the directory service with the rights of this user. Make sure to specify the corresponding password.

Settings tab

Specify the settings for searching directory services for user attribute values to return corresponding name and address attribute values.

For guidance on filling in the **User search filter** and **User attribute** fields, click on the **Default** button to display the **Display Directory Service** dialog box. Select a directory service name in the list of available directory services and click on **OK**.

Selecting a directory service, for example Active Directory, populates the User search filter and User attribute fields with default values for the selected directory service. You can edit the values if you have customized your directory service and require different values.

Attributes

Option	Description
Name attribute	Specify or edit the name attribute.
Address attribute	Specify or edit the address attribute designation.
Search name prefix	Specify or edit any prefix (e.g. cn=) that should be added before search values.

Remote Control tab

Use the **Remote Control** tab to specify general remote control session options.

NOTE: You can specify individual remote control session options for each **Host** connection in the **Connection Properties** dialog box, which you can access either by clicking the **Connec-**

tion Properties dialog box on the **Quick Connect** tab, or in a running remote control session, by clicking on the **Connection Properties** button from the toolbar.

Enable

Option	Description
Toolbar	Select this check box to display the Remote Control window toolbar.
Toolbox in full screen	Select this check box to display the Remote Control full screen display toolbar.
Full screen toolbox roll-up	Select this check box to reduce the Remote Control full screen display toolbar to the corresponding title bar when not in use.
Status line	Select this check box to display the Remote Control window status bar.

Hot keys assignment

You can assign hotkeys (keystroke combinations) to specified actions. By default, CTRL+Z is assigned to Zoom in and out (switch between Remote Control window and full screen). Assign desired hotkeys by selecting check boxes and specifying a character in the last field.

Remote control window

Option	Description
Host window auto scroll	Select this check box to enable automatic Host screen image scroll when the mouse pointer approaches Remote Control window borders.
Show full screen as top-most window	Select this check box to display the Remote Control full screen display in front of any other window.
Show full screen on all monitors	Select this check box to display the Remote Control full screen display on all available monitors.
Auto take control	Select this check box to enable acquiring multi Guest session keyboard and mouse control by a keystroke or mouse click.
Switch to window mode password	Specify a password that should be requested to switch from full screen to window. The field displays password characters as dots or asterisks.
Disconnect password	Specify a password that should be requested to disconnect. The field displays the password characters as dots or asterisks.

Clipboard tab

Use the **Clipboard** tab to specify remote control clipboard transfer options.

Automatic clipboard transfer

Option	Description
Automatically transfer clipboards below	Select this check box to enable contents placed on the Guest computer or Host computer clipboard during a remote control session to automatically become the clipboard contents of both computers if smaller than the number of kilobytes specified in the field.
Show progress dialog during transfer	Select this check box to display a small window with a progress bar while clipboard contents are being transferred from one computer to the other.

Monitor tab

Use the **Monitor** tab to specify monitor options.

Option	Description
Monitor interval	Specify a number of seconds in the range 1-999 after which to switch to the next Host after monitoring a Host (default: 15).
Start Monitor in full screen	Select this check box to initially display monitored Host screen images in full screen mode. If unchecked, Host screen images are initially shown in window mode.

Audio-Video Chat tab

Use the **Audio-Video Chat** tab to specify audio and video chat options.

Audio-video chat settings

Option	Description
Start audio chat when conference is started	Select this check box to enable sound transfer at session start.
Start video when conference is started	Select this check box to enable image transfer at session start.

Audio Chat

Select the **Enable full-duplex audio** check box to enable sound transfer in both directions at

the same time.

NOTE: Some computer sound systems do not support full-duplex audio.

Microphone sensitivity

Option	Description
Silence level	Drag the slider bar to specify the microphone sound input level below which no sound data should be transferred.
Line hold	Drag the slider bar to specify the time period in which sound data should continue to be transferred after the microphone sound input level has dropped below the silence level. TIP: Try out different Silence level and Line hold settings to optimize sound transfer.
Check sound system	Click on this button to check the computer sound system. A result message is displayed.
Advanced	Click on this button to display the Advanced audio settings dialog box. See Advanced audio settings .

Video

Option	Description
Capture size	Select a video capture frame size on the list. The size is displayed in pixels (default: 160 x 120).
Advanced	Click on this button to display the Advanced Video dialog box. See Advanced Video .

Remote Printing tab

Use the **Remote Printing** tab to specify remote Netop printers and incoming print job redirection.

Remote Netop printers

You can add a Netop printer on the **Guest** computer to enable sending a **Guest** computer print job to a **Host** computer printing device (remote printer).

Click on the **Add printer** button and following the instructions in the displayed **Add printer guidelines** window. Click on the **Ready** button to start adding a Netop printer.

The **Remote Netop printers** pane displays the names of Netop printers in the Windows Print-

ers folder on the **Guest** computer.

NOTE: You can also add a Netop printer on a **Host** computer to enable sending a Host computer print job to a **Guest** computer printing device. You can remove a Netop printer by selecting the printer in the pane and clicking on the **Remove printer** button.

If you are connected to multiple **Hosts** while sending a print job to a Netop printer, a dialog box prompting you to select the Host to which you want to send the print job is displayed.

NOTE: Special instructions for remote printing from DOS applications are available in the Netop KnowledgeBase.

Redirect print to

You can redirect a print job sent from the **Host** computer to the **Guest** computer to any printer specified on the **Guest** computer.

Option	Description
Default printer	Select this option to redirect the print job to the default Guest computer printer.
Prompt with a list of available printers	Select this option and click on Browse to display the Select Print Redirection Printer dialog box. From the Select Print Redirection Printer dialog box, you can select a printer from a list of available printers.

See also

[Send a print job to a remote printer](#)

Recording tab

Use the **Recording** tab to specify remote control session recording options.

Options

Option	Description
Use compatible mode	Remote control session recording was improved in Netop Remote Control version 8. Older Guest versions cannot play back version 8+ recordings. Select this check box to make older version compatible recordings.
Enforce recording	Select this check box to record all remote control sessions even if the Record remote control session check box is not selected (Connection Properties > Record tab).

Disconnect if recording fails	Select this check box to disconnect if recording a remote control session fails.
-------------------------------	--

Recording

A **Recordings** tab record and recording file name will identify the remote control session **Guest**.

Select one of these identity options:

Option	Description
Guest ID	Identify by the Guest ID. See Logon tab for further information.
Guest user	Identify by the Guest computer Windows or network logon user name.

See also

[Record sessions](#)

Sounds tab

Use the **Sounds** tab to specify sounds played upon selected events.

Select an event check box to play a sound upon the event. Clear the selection to suppress playing a sound upon the event.

Select an event and click on **Select Sound** to open a sound file with the extension ***.wav** to replace the current sound. The event is marked with an asterisk (*). Select an event marked (*) and click on **Default Sound** to reassign the default sound to the event and remove the (*) mark.

If you want to listen to the sound while editing the sound settings, select an event and click on **Play** to play the sound assigned to the event.

Help Request tab

Use the **Help Request** tab to set up use of help request.

Select the **Enable help request** check box to enable the **Guest** to receive help requests.

Click on the **Advanced** button to display the **Advanced Help Service** dialog box allowing you to specify actions that are to be executed when a help request arrives. See [Advanced Help Service](#).

Help Service tab

The **Guest** can receive **Host** help requests only if the **Enable help request** and **Enable help services** check boxes are selected, at least one Help service name is specified and communication profiles are enabled at **Guest** loading.

The **Host** uses the term help provider for a help service name.

Option	Description
--------	-------------

Enable help services	Select this check box to enable the help services specified below.
Help service 1-3	In these fields, specify the names of the help services that this Guest is to offer.

Service Ticket tab

The extended **Guest** also has a **Service Tickets** tab that enables it to service help requests by service ticket numbers. Service tickets are used for both Netop Remote Control and Netop OnDemand Remote Control (1.74 and earlier versions).

Option	Description
Enable service tickets	Select this check box to enable the use of service tickets to service help requests through a service ticket number.
Service ticket format	Enter a service ticket format using any character plus the control characters #, @, and * (# produces a number (0-9), @ produces a letter (A-Z) and * produces a number or a letter (0-9, A-Z)), for example @##-****. The service ticket generated from this can only be used once, after which a new ticket is generated.
Number of auto generated service tickets	Enter the number (0-3, 0 = manually) of service tickets to be auto-generated.

WebConnect tab

The extended **Guest** also has a **WebConnect** tab that enables it to service help requests by **WebConnect** tickets. **WebConnect** tickets are used for Netop OnDemand Remote Control 2.0 and later versions.

Option	Description
Enable WebConnect tickets	Select this check box to enable use of WebConnect tickets.
WebConnect ticket	Enter anything that you want to use as a WebConnect ticket for identification purposes during a Netop OnDemand remote control session using WebConnect, for example an email address, a name, or a keyword, for example Security Server.
WebConnect profile	Select a WebConnect profile in the list. The WebConnect profile contains the credentials and the Connection Manager URL to be used for the WebConnect connection. The profile itself should be defined in the Setup Wizard before you can select it here. You can also set up the profile in Communication Profiles . One or more WebConnect profiles can be defined in Communication

	Profiles. See Communication Profile Edit for more information.
Update interval	Enter an interval in seconds to specify how often the Guest should communicate with WebConnect and check for new tickets.

See also

[Set up Help Request on Guest and Host](#)

Run tab

Use the **Run** tab to specify programs to include in the **Run Program** drop-down menu on the **Guest** window and **Remote Control** window toolbars.

The pane displays specified programs as records in a table with a description and the program file path and name.

NOTE: Table contents are stored in the runprog.ndb Netop configuration file: C:\Documents and Settings\\Application Data\Netop\Netop Remote Control\Guest.

Click on the **Add** button to add a program to the pane. The **Run** dialog box in which you can specify a program to run is displayed. See [Run](#).

To see the properties of a record in the pane, select the record and click on the **Properties** button. The **Run** dialog box is displayed, and you can edit the properties specified.

To delete a record again, select it in the pane and click on the **Delete** button.

See also

[Run a program on one or multiple Hosts](#)

Encryption tab

Use the **Encryption** tab to enable encryption types.

The communication between Netop modules is protected by encrypting transmitted data.

A range of encryption types is available on Netop Remote Control modules.

Communicating Netop modules automatically negotiate to encrypt communication by an encryption type that is enabled on both modules. See [Connection Properties \(Compression/Encryption tab\)](#). Netop modules on which no common encryption type is enabled cannot communicate.

Select the check boxes next to the various encryption types to enable them.

To see encryption details about the individual encryption types, select an encryption type and click on the **Show Details** button.

Inventory tab

Use the Inventory tab to specify what inventories should contain and how the contents should be displayed in the **Guest** window Inventory tab.

Summary view

The pane contains a list of available inventory details. Select check boxes to specify the inventory details of the **Guest** window Inventory tab summary, which is displayed in the details pane on the right when a folder is selected in the contents pane on the left.

The pane top-to-bottom order of selected inventory details determines the left-to-right order of details pane columns.

Use the **Up/Down**, **Select All**, **Deselect All** buttons to arrange the contents of the pane.

Click on the **Advanced** button to specify inventory processing and custom inventory items. The **Advanced inventory** option dialog box is displayed. See [Advanced inventory](#) option.

See also

[Generate a Host inventory](#)

Smart Card tab

Use the **Smart Card** tab to specify the Smart Card reader whose reading applies to the Smart Card authentication.

Smart Card Reader

Option	Description
Select Smart Card reader	In the drop-down list, select the Smart Card reader that you want to use. The list contains Default and the names of connected Smart Card readers found by Windows.
Support Remote Smart Card Logon	Select this check box to enable remote Smart Card logon. This means that using a local Smart Card reader you can log directly into remote enterprise and application systems using a Smart Card for authentication and authorization.

Intel vPro tab

Use the **Intel vPro** tab to specify the address of the SCS Web Service.

Select the **Connect to SCS** check box and enter the SCS Web Service URL in the field below.

The address is then saved in the system, so that every time you select the **Retrieve Intel vPro Enabled Computers from SCS** command on the context menu for the **Intel vPro** tab pane on

the **Quick Connect** tab, you aren't prompted to enter the address.

See also

[Use Intel vPro from Netop Remote Control](#)

Skins tab

If you run a remote control session, skins enable you to see the **Host** device and execute commands on the **Host** device by clicking the buttons on the applied skin. A device may have more than one skin definition depending on its state, for example slide out keyboard, portrait and landscape orientation etc. Every time the device changes state, the **Host** sends updated skin information to the **Guest**.

If the **Guest** does not have the skin that is needed for a remote control session with a particular **Host**, it attempts to collect a suitable skin from the Netop Skin Repository Server. If the necessary skin is not available, the **Guest** uses a default skin.

On the **Skins** tab, the address and port number of the Netop Skin Repository Server are displayed.

Click on the **View Models** button if you want to see the available skin models.

Web Update tab

Use the Web Update tab to specify web update options to automatically update the Guest installation.

Option	Description
Update server	<p>Specify the web address of the server from which to download Guest update files (default: <code>update.netop.com</code>, the Netop manufacturer web update server).</p> <p>NOTE: To update many Netop installations in an organization, we recommend publishing new updates to an internal web update server (select Publish New Updates on the Tools menu).</p>
HTTP Proxy	<p>Specifying a HTTP proxy is typically not required.</p> <p>Before specifying a HTTP proxy, click on Update now to test the web update connection. If you receive a message indicating connection to the update server, specify no HTTP proxy.</p> <p>If Update now yields no connection, click on the Detect button to make Netop attempt to detect the HTTP proxy server and display its name and port number in the HTTP Proxy field.</p> <p>Click on Update now to test the connection. If unsuccessful, consult</p>

	your network/system administrator about what to specify in the HTTP Proxy field (format: <Server name>:<Port number>).
Update now	Click on this button to connect to the update server specified in the Update server field. A web update message notifies you if the connection to the update server fails, if no updates are available or if updates are available, and in the latter case ask you if you want to download and install updates.
Schedule	Click on this button to display the Web Update Schedule dialog box and specify a schedule of checks for updates including download and installation of available update files.

5.1.20 Run

Use the **Run** dialog box to specify a program file to run using the **Run Program** function and how the program should start.

File

Type a descriptive text in the **Description** field. This text appears on the menu.

File name

Make sure that the Local file name option has been selected and then click on the **Browse** button to locate the program .exe file.

When the program file is added to the **Local file name** field, the global file name is automatically added to the **Global file name** field. The absolute path is replaced with environment variables. This is especially helpful if your computers are running different Windows platforms.

Example of a local file name and the corresponding global file name:

```
C:\Program Files\Adobe\Acrobat 6.0\Reader\AcroRd32.exe
%ProgramFiles%\Adobe\Acrobat 6.0\Reader\AcroRd32.exe
```

TIP: Once you have added a program to the **Local file name** field and the global file name has been added automatically to the **Global file name** field, select the **Global file name** option, so that you do not have to consider which operating system version or operating system language **Host** computers are using.

If the selected program needs to be started using command line switches, use the **Command**

line switches field to type those. This could for example be starting Internet Explorer with a specific address or for Adobe Acrobat Reader, the name of the document to read.

Run

Under **Run**, select **Normal**, **Maximized** or **Minimized** to define how the program should start when opened from the **Run Program** button in the toolbar or from the Run Program command on the **Connection** menu.

5.1.21 Script

A script is a user specified command structure that can execute a task, typically an unattended scheduled file transfer.

Use the **Script** dialog box to create and edit scripts in a graphical tree structure.

Option	Description
Filename	Specify a script file name. If you do not specify a file extension and a path, the script file gets the extension <code>.dws</code> and is located in the Netop configuration files folder, typically <code>C:\Documents and Settings\<user name="">\Application Data\Netop\Netop Remote Control\Guest\script\</user></code> . If you create a new script, you are prompted for confirmation. Click on Yes . The Global Settings dialog box is then displayed.
Open Script	Click on this button to open a script file.
Comment	Enter a comment about the script. The comment is displayed in the Comments column in the Script tab (Optional).
Save Script	Click on the Save Script button to save a new or edited script.
Add	Click on the Add button to add a script command in the upper pane under the selected script command. See Commands list below.
Edit	Select a script command in the upper pane and click on the Edit button to display the corresponding editing window.
Run Script	Click on this button to run the script.
Delete	Select a script command in the upper pane and click on the Delete button to delete it, including the command sub tree under it.

Commands list

To specify the first command of a script, in the upper pane of the **Script** dialog box, select the **Global Settings** element and click on the **Add to display** a drop-down menu.

This menu contains script commands that can execute on the **Guest**:

Connect	Select the Connect command to add a Connect command, which connects to a Host .
Wait	Select the Wait command to add a Wait command, which delays script execution.
Run	Select the Run command to add a Run command.

A **Connect** command branches the script into commands that execute with or on the connected Host computer or in case of a local **Connect** command on the **Guest** computer.

In the upper pane, click the **+** (plus) next to a **Connect** command to expand it and select the expanded **Connect** command or a command below it.

Click on **Add** to display the following menu, which contains script commands that can execute with a connected **Host** or a **Guest** connected locally to itself:

Copy	Select one of these commands to display a <File transfer> dialog box and add a File Transfer command.
Move	
Synch	
Clone	
Delete	
Wait	Select this command to display the Wait dialog box and add a Wait command to delay script execution.
Run	Select this command to display the Run Program dialog box and add a Run command to execute a program on the connected to computer. You can schedule scripts to be ran from the Guest on the Host by using elevated privileges; select Use a different account and enter the credentials of a user with elevated privileges on the Host machine.
Logoff	Select one of these commands to add an Action command to execute an action on the connected to computer.
Restart	
Poweroff	

Lock	
Inventory	
Send Message	

See also[Create and run a script](#)[Global Settings](#)[Netop File Manager Options](#)**5.1.22 Send Message**

When you add a **Send Message** command to a script, the **Send Message** dialog box is displayed allowing you to specify how the message should be sent.

Option	Description
	<p>Select a Send Message step option in the drop-down list:</p> <ul style="list-style-type: none"> • One Step: Select this option to copy a message file on the Guest computer to the Messages directory on the Host computer and display it in a Send Message window on the Host computer screen. <p>NOTE: Create and save the message file in the Message window.</p> <ul style="list-style-type: none"> • Display Message: Select this option to display a message file located on the Host computer in the Messages directory in a Message window on the Host computer screen.
Message path	<p>Specify the Guest computer (One Step) or Host computer (Display Message) path and name of the message file to (copy and) display.</p> <p>Click on the Browse button to open a message file on the Guest computer and display its path and name in the field.</p> <p>NOTE: The Host computer Messages directory, which is located in the Netop configuration files directory, typically C:\Documents and Settings\All Users\Application Data\Netop\Netop Remote Control\Host\Messages, is identified by the environment variable %RootConfig%Messages. To display in the Message window on the Host computer screen, the message file name must use the syntax <Date>T<Time>;<Sender>.rtf with the date format YYYY-MM-DD and the time format HH-MM-SS.</p>

See also[Script](#)[Create and run a script](#)

[Communicate with Host users](#)

5.2 Host dialog boxes

5.2.1 Advanced Help Request Options

Communication

Option	Description
Phone number or IP address	If requesting help by a communication profile that uses a point-to-point or network point-to-point communication device other than Infrared (IrDA), a telephone number or IP address should be specified. If not specified in this field, the Connect to Help Provider dialog box is displayed when requesting help, and you can specify the telephone number or IP address there.
Help request timeout if not answered	Specify a number in the range to cancel the help request if not responded to by a help provider within the specified number of minutes (default: 0, i.e. the help request does not get canceled).

Gateway logon

If requesting help by a communication profile that uses a point-to-point or network point-to-point communication device through a **Guest** network Netop Gateway, it may request logon.

Specify Gateway logon name, password and domain in this section.

If valid Gateway logon credentials are not specified here, a Gateway logon dialog box may be displayed when requesting help, and you can specify the credentials there.

Select the **Use current logon credentials for Windows Security authentication** check box to log on by the name, password and domain of the user logged on to Windows on the **Host** computer.

See also

[Program Options](#) (Help Request tab)
[Request help](#)

5.2.2 Allowed ISDN Numbers

If **Guest ISDN number check** is enabled in the **Communication Profile Edit** dialog box for ISDN, a **Host** and a connecting Gateway can allow connections by ISDN (CAPI) communication only from telephone numbers in the **Allowed ISDN Numbers** list.

The **Allowed Network Numbers** dialog box displays allowed ISDN telephone numbers. You can add, edit and delete ISDN telephone numbers in the dialog box.

NOTE: Allowed ISDN numbers are stored in the Netop configuration file `anumlist.ndb`, which is typically located in the directory `C:\Documents and Settings\All Users\Application Data\Netop\Netop Remote Control\<Module name>`.

See also

[Communication Profile Edit](#)

5.2.3 Directory Service

Use the **Directory Service** dialog box to specify a directory service.

General

Option	Description
Name	Specify the name that should identify the directory service in Directory Services tab pane.
Directory server	Specify the directory server IP address or DNS name.
Port	Specify the port through which the Host should connect to this directory server (default: 389, the Lightweight Directory Access Protocol (LDAP) port). Select the Use secure connection check box to connect to the directory server by a secure connection. The LDAP secure connection port number is 636.
Base DN	Specify the directory service distinguished name from which a search should start.

Credentials tab

Use the **Credentials** tab to specify the credentials by which the **Host** should log on to the directory server. The credentials determine what directory service information is available to the **Host**.

Option	Description
Anonymous bind	Select this check box to search the specified directory service with anonymous user rights, which are typically very limited.
User DN	Specify a directory service user distinguished name to search the directory service with the rights of this user.
Password/Confirm password	Specify the corresponding password and confirm it.

Settings tab

Use the **Settings** tab to specify the search criteria that should be applied to retrieve the properties of a connecting Guest user. Initially, the fields are empty.

Click on the **Default** button to display the **Select Directory Service** dialog box.

The drop-down list contains names of commonly used directory services such as Microsoft Active Directory. Select a directory service type in the drop-down list. If the directory service type of the directory server specified in the **Directory Server** field of the **Directory Service** dialog box is available in the list, select this in the list.

Click on the **OK** button to close the dialog box and specify the default settings of the selected directory service type in the **Settings** tab fields.

NOTE: If the **Settings** tab fields are filled in when you select a directory service type in the **Select Directory Service** dialog box, you typically do not need to edit their contents.

Option	Description
User search filter	Optionally (recommended), specify a search filter to limit the search for user attributes to a certain object class.
User attribute	Specify the type designation of the searched for user attribute.
User browse filter	Optionally (recommended), specify a user browse filter to limit the browse for user attributes to certain object classes.
Group search filter	Optionally (recommended), specify a search filter to limit the search for group attributes to a certain object class.
Group attribute	Specify the type designation of the searched for group attribute.
Group browse filter	Optionally (recommended), specify a group browse filter to limit the browse for group attributes to certain object classes.
OU search filter	Optionally (recommended), specify a search filter to limit the search for organizational unit attributes to a certain object class.

See also

[Program Options](#) (Directory Services tab)

5.2.4 Guest Access Security

Guest Access Privileges tab

Use the **Guest Access Privileges** tab to select the Guest access method to apply to connecting **Guests**.

Select a method from the **Guest Access Method** list:

<p>Grant all Guests default access privileges</p>	<p>This selection means that the Guests share the same privileges and use the same password to log on to the Host.</p> <p>When a Guest connects, the Host requests a password. If the Guest returns the password set up for the default user, the Host grants the Guest the privileges set up for the default security role.</p> <p>Setup</p> <p>In the left pane, select Default Security Role to display the access privileges of this security role, i.e. what Guests are allowed to do when connecting to the Host, in the right pane.</p> <p>The Confirm access section in the right pane specifies whether and when access to the Host computer needs confirmation.</p> <p>NOTE: For practical reasons, the Netop message and Get inventory functions are exempted from Confirm access security, as these are often used when there is no user present on the Host side.</p> <p>The Whitelisted applications section in the right pane specifies whether the Remote Control sessions for this role are limited solely to the whitelisted applications defined in the whitelisted.txt file, found in the Netop configuration files folder: C:\ProgramData\Danware Data\C\Program Files (x86)\Netop\Netop Remote Control\<module name>.<="" p=""> <p>NOTE: Refer to the Netop Knowledge Base for more information about whitelisting.</p> <p>Select Default User in the left pane to set password and call back options. In the right pane, specify a password of max. 64 characters to enable shared password authentication.</p> </module></p>
---	--

	<p>To disable shared password authentication and request no password from a connecting Guest, clear both password fields. This, however, leaves the Host without Guest access authentication, and any Guest can then connect to the Host. Unless suppressed, a security warning is displayed when the Host starts communicating.</p> <p>The Call back section below the Password section specifies whether or not to use call back.</p> <table border="1" data-bbox="523 555 1415 1720"> <thead> <tr> <th data-bbox="523 555 730 607">Option</th> <th data-bbox="730 555 1415 607">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="523 607 730 658">No call back</td> <td data-bbox="730 607 1415 658">Do not apply call back.</td> </tr> <tr> <td data-bbox="523 658 730 1106">Call back to</td> <td data-bbox="730 658 1415 1106">Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address to enable connections only from a Guest on a computer with this telephone number or IP address.</td> </tr> <tr> <td data-bbox="523 1106 730 1720">Roving call back</td> <td data-bbox="730 1106 1415 1720">Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.</td> </tr> </tbody> </table>	Option	Description	No call back	Do not apply call back.	Call back to	Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address to enable connections only from a Guest on a computer with this telephone number or IP address.	Roving call back	Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.
Option	Description								
No call back	Do not apply call back.								
Call back to	Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address to enable connections only from a Guest on a computer with this telephone number or IP address.								
Roving call back	Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.								
Grant each Guest individual access privileges using Netop authentication	<p>This selection means that each Guest has its own privileges and password to log on to the Host.</p> <p>When a Guest connects, the Host requests the Netop credentials, i.e. ID and password, defined for that specific Guest. When the Guest returns the required information, the Host grants the Guest</p>								

	<p>the privileges set up for the specific Guest.</p> <p>Setup</p> <p>Each security role specifies what is allowed to the Guest and the selected confirm access option. Each Guest profile specifies Guest logon credentials and the selected call back option.</p> <p>Initially, the left pane contains the security role folders Full access, View only, Inventory only and Remote Management only. You can add a security role by clicking on the Add security role button and defining the new security role by clearing the check boxes in the right pane.</p> <p>The Confirm access section in the right pane specifies whether and when access to the Host computer needs confirmation.</p> <p>NOTE: For practical reasons, the Netop message and Get inventory functions are exempted from Confirm access security, as these are often used when there is no user present on the Host side.</p> <p>The Whitelisted applications section in the right pane specifies whether the Remote Control sessions for this role are limited only to whitelisted applications defined in the whitelisted.txt file, found in the Netop configuration files folder: C:\ProgramData\Danware Data\C\Program Files (x86)\Netop\Netop Remote Control\<Modulename> folder.</p> <p>You can add Guests to a security role by selecting it and clicking on the Add Guest button. In the displayed Guest Profile dialog box, specify the Guest name, password and call back option.</p> <p>See Guest Profile.</p> <p>Select a Guest profile element in the left pane to display its Password section and the Call back section to the right.</p>
<p>Grant each Guest individual access privileges using Windows Security Management</p>	<p>This selection means that each Guest has its own privileges and logs on to the Host by its Windows logon user credentials.</p> <p>When a Guest connects, the Host requests the Windows user name, password and domain. If a match is found in Windows Se-</p>

curity Management, the Host grants the **Guest** the privileges of the security role assigned to the Windows account object.

A **Guest** user who is assigned different security roles individually and as a member of groups is allowed what is allowed by any of the applicable security roles, i.e. the sum of privileges of the applicable security roles.

Setup

Each security role specifies what is allowed to the **Guest** and the selected confirm access option.

Initially, the left pane contains the security role folders **Full access**, **View only**, **Inventory only** and **Remote Management** only. Select a security role folder to display the privileges in the right pane. You can add a security role by clicking on the **Add security** role button and defining the new security role by clearing check boxes in the right pane.

The **Confirm access** section in the right pane specifies whether and when access to the **Host** computer needs confirmation.

NOTE: For practical reasons, the Netop message and **Get inventory** functions have been exempted from Confirm access security, as these are often used when there is no user present on the **Host** side.

The Whitelisted applications section in the right pane specifies whether the Remote Control sessions for this role are limited only to whitelisted applications defined in the whitelisted.txt file, found in the Netop configuration files folder: C:\ProgramData\Danware Data\C\Program Files (x86)\Netop\Netop Remote Control\<Modulename>.

You can add a user or group to a security role by selecting it and clicking on the **Add User** or **Add Group** button. In the Select Users or Select Groups dialog box, specify the users or groups you want to add.

Select a Windows user or group element to display its Domain section, RAS section and Call back section to the right.

The Domain section displays the domain of the selected Windows user or group.

The RAS section is only included if the Host computer runs on a Windows NT, 2000, XP, 2003, 2008, Vista or 7 operating system. Select the **Get call back information from Windows NT Remote Access Service (RAS)** check box to use call back information stored in Windows NT Remote Access Service.

The **Call back** section is displayed only if the check box in the RAS section is not selected.

Specify whether or not to use call back.

Option	Description
No call back	Do not apply call back.
Call back to	Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address enables connections only from a Guest on a computer with this telephone number or IP address.
Roving call back	Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.

The Windows User Manager button is included only if the **Host** computer runs on a Windows NT, 2000, XP, 2003, 2008, Vista or 7 operating system. Click on this button to display the Windows user manager window according to the administrator rights of the user logged on to Windows on the **Host** computer to manage users and groups.

Grant each Guest individual access privileges using Directory services

This selection means that each **Guest** has its own privileges and logs on to the **Host** by directory services user credentials.

When a **Guest** connects, the **Host** requests the directory service user name, password and directory server for that specific **Guest**. If a match is found on the directory server, the **Host** grants the **Guest** the privileges of the security role assigned to the directory services account element.

A **Guest** user who is assigned different security roles individually and as a member of groups is allowed what is allowed by any of the applicable security roles, i.e. the sum of privileges of the applicable security roles.

Setup

Each security role specifies what is allowed to the **Guest** and the selected confirm access option.

Initially, the left pane contains the security role folders Full access, View only, Inventory only and Remote Management only. Select a security role folder to display the privileges in the right pane. You can add a security role by clicking on the **Add security role** button and defining the new security role by clearing check boxes in the right pane.

The **Confirm access** section in the right pane specifies whether and when access to the **Host** computer needs confirmation.

NOTE: For practical reasons, the Netop message and **Get inventory** functions have been exempted from Confirm access security, as these are often used when there is no user present on the **Host** side.

The Whitelisted applications section in the right pane specifies whether the Remote Control sessions for this role are limited only to whitelisted applications defined in the whitelisted.txt file, found in the Netop configuration files folder: C:\ProgramData\Danware Data\C\Program Files (x86)\Netop\Netop Remote Control\<Module name>.

You can add a user or group to a security role by selecting it and

	<p>clicking on the Add User or Add Group button. In the displayed Select Directory Services Users or Select Directory Services Groups dialog box, specify the users or groups you want to add.</p> <p>Select a directory services user or group element to display its Directory service section and Call back section to the right.</p> <p>The Directory Service section displays the directory service name and the selected directory services user or group element distinguished name (dn).</p> <p>Specify whether or not to use call back:</p> <table border="1" data-bbox="523 651 1417 1780"> <thead> <tr> <th data-bbox="523 651 721 703">Option</th> <th data-bbox="721 651 1417 703">Description</th> </tr> </thead> <tbody> <tr> <td data-bbox="523 703 721 754">No call back</td> <td data-bbox="721 703 1417 754">Do not apply call back.</td> </tr> <tr> <td data-bbox="523 754 721 1216">Call back to</td> <td data-bbox="721 754 1417 1216">Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address enables connections only from a Guest on a computer with this telephone number or IP address.</td> </tr> <tr> <td data-bbox="523 1216 721 1780">Roving call back</td> <td data-bbox="721 1216 1417 1780">Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.</td> </tr> </tbody> </table>	Option	Description	No call back	Do not apply call back.	Call back to	Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address enables connections only from a Guest on a computer with this telephone number or IP address.	Roving call back	Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.
Option	Description								
No call back	Do not apply call back.								
Call back to	Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address enables connections only from a Guest on a computer with this telephone number or IP address.								
Roving call back	Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, e.g. when a traveling employee connects to the home computer.								
Use the Netop Security Server	<p>This selection means that the Host uses the Netop Security Server to authenticate each connecting Guest and assign a security role to it.</p> <p>When a Guest connects, the Host requests logon credentials ac-</p>								

	<p>According to Netop Security Management preferences.</p> <p>Refer to the Administrator's Guide for further information about Netop Security Management.</p> <p>The Host forwards returned credentials to Netop Security Server for validation and compilation of the security role that is to be assigned to the Guest according to the security data stored in the security database. The Host applies the resulting security role to the Guest.</p> <p>Setup</p> <p>The Public Key field is used to secure a trusted connection between your Hosts and Security Servers.</p> <p>NOTE: In production environments, we recommend that you replace the default Public Key with a newly generated Public Key using the Security Manager.</p> <p>The Public Key should be copied to the Hosts exactly as it is shown in the Security Manager. It is recommended that you change the Public Key before deploying your Hosts.</p> <p>Refer to the Netop Security Management section in the Administrator's Guide for more information about generating a Public Key from the Security Manager.</p>
<p>Use the Netop Portal access rights</p>	<p>This selection means that the Host uses the Netop Portal to authenticate each connecting Guest and assign permissions to it.</p> <p>When a Guest connects, the Host requests logon credentials according to the Netop Portal account.</p> <p>Refer to the Netop Remote Control Portal User's Guide for more information about the Netop Portal.</p> <p>The Host forwards returned credentials to Netop Portal for validation and compilation of the security permissions that are to be assigned to the Guest. The Host applies the resulting security permissions to the Guest.</p>

Guest Policy tab

Use the **Guest Policy** tab to specify **Guest** access security policies. The policy functions determine how the **Host** behaves before, during and after the remote control session.

Password

Option	Description
Maximum invalid password attempts	Specify a number in the range 0 - 9 for the number of logon attempts that can be allowed to a Guest before the action selected in the drop-down list below is executed.
Action if maximum attempts are exceeded	In the drop-down list, select what should happen if maximum password attempts are exceeded: <ul style="list-style-type: none"> • Disconnect: Disconnect the Guest. • Disable Host: Make the Host reject any connection attempt. • Restart Windows: Restart Windows on the Host computer, which - depending on the Host setup - may load and start the Host and make it available for connection.

Disconnect

Option	Description
Action after disconnect	In the drop-down list, select what should happen after disconnect: <ul style="list-style-type: none"> • None: No action. • Lock computer: Lock the Host computer. The Windows Computer Locked window is displayed. The Host keeps running and is available for connection. • Log off Windows: Log off the Host computer user from Windows. The Welcome to Windows window is displayed. The Host keeps running and is available for connection. • Restart Windows: Restart Windows on the Host computer, which - depending on the Host setup - can load and start the Host and make it available for connection.
System-wide disconnect hotkey	Select any of the first four check boxes and optionally specify a character in the last check box to compose a keystroke combination that will disconnect all connected Guests whether the Host

	window is active or not.
--	--------------------------

File Transfer

Select the **Disable file transfer before local logon** check box to disable file transfer if no user is logged on to the Host computer.

Record Sessions

Option	Description
Enable	Select this check box to enable Host recording of remote control sessions. If you enable the Record Sessions function, you can document any unauthorized procedures that a Guest could carry out on the Host .
Folder	Specify the path of the directory in which to save the session recording files. Click on the Browse button to select a folder.
Disconnect if recording fails	Select this check box to disconnect if session recording fails. NOTE: Session recording files are named <Time stamp>-<Guest ID>-<Host ID>.dwr. You can only play back session recording files on a Guest .

Timeout

Option	Description
Confirm Access	Specify a number in the range 1 - 9999 to disconnect if the Host user has not confirmed Guest access within the specified number of seconds.
Authentication	Specify a number in the range 1 - 9999 to disconnect if Guest authentication has not completed within the specified number of seconds.
Inactivity	Specify a number in the range 1 - 9999 to disconnect if there has been no Guest keyboard or mouse activity within the specified number of seconds.

MAC/IP Address List Setup tab

MAC/IP Address List

Select the **Enable MAC/IP address** check check box to limit the network addresses from which a **Guest** can connect to the addresses specified in the pane.

Click on the **Add** button to specify MAC/IP addresses.

MAC addresses are applied if they communicate by NetBIOS or IPX. IP addresses apply if they communicate by TCP/IP or TCP/IP (TCP).

Encryption tab

The communication between Netop modules is protected by encrypting transmitted data.

A range of encryption types is available on Netop Remote Control modules.

Communicating Netop modules automatically negotiate to encrypt the communication by an encryption type that is enabled on both modules. Netop modules on which no common encryption type is enabled cannot communicate.

Select the check boxes next to the various encryption types to enable them.

To see encryption details about the individual encryption types, select an encryption type and click on the **Show Details** button.

Smart Card

Use the **Smart Card** tab to specify Smart Card logon options to use Smart Card for authentication with Windows Security Management or Directory Services.

Windows Security Management

If you have selected the Guest access method **Grant each Guest individual access privileges** using Windows Security Management on the **Guest Access Privileges** tab, select an option in this section.

Option	Description
Never log on with Smart Card	Enable only credentials logon.
Always log on with Smart Card	Enable only Smart Card logon.
Allow both logon with Smart Card and credentials (name, password, and domain)	Enable both credentials and Smart Card logon.

Directory Services

If you have selected the **Guest** access method Grant each **Guest** individual access privileges using Directory services on the **Guest Access Privileges** tab, select an option in this section.

Option	Description
Never log on with Smart Card	Enable only credentials logon.

Always log on with Smart Card	Enable only Smart Card logon.
Allow both logon with Smart Card and credentials (name, password and server)	Enable both credentials and Smart Card logon.
Subject Field	Retrieve the user identification from the Subject field of the Smart Card certificate.
Subject Alternative Name Field (must be a User Principal Name (UPN))	Retrieve the user identification from the Subject Alternative Name field of the Smart Card certificate.
The Certificate Field matches this Directory Services Attribute	<p>Specify the directory services attribute compatible with the Smart Card certificate field contents. This is necessary only if different from a user object distinguished name.</p> <p>For Directory Services Smart Card logon to succeed, make sure that Host can resolve the Smart Card certificate user identification into a Directory Services user identification. If the Smart Card certificate user identification and Directory Services user identifications are incompatible, Smart Card logon fails.</p> <p>To find the available Smart Card certificate user identifications, insert the Smart Card and in Internet Explorer click on the Internet Options command on the Tools menu to display the Internet Options dialog box.</p> <p>On the Content tab, click Certificates to display the Certificates dialog box.</p> <p>On the Personal tab, double-click on the appropriate certificate record to display the Certificate dialog box. The Details tab displays the contents of available certificate fields including Subject and Subject Alternative Name.</p>

[See also](#)
[Program Options](#) (Smart Card tab)

5.2.5 Guest Profile

Use this dialog box to create a **Guest** profile element in the security role folder that you selected on the **Guest Access Privileges** tab.

Guest name

In the **Guest ID** field, specify the name that a **Guest** is using this **Guest** profile should specify to log on to the **Host**. This is the name that identifies the **Guest** profile.

NOTE: A **Guest** is not limited to logging on by the name that identifies the **Guest**. The **Guest** logon does not verify **Guest** identity but validates the **Guest** credentials.

Password

In the **Password** section, specify a password of max. 64 characters to enable password authentication.

Call back

In the **Call back** section specify whether or not to use callback.

Option	Description
No call back	Do not apply call back.
Call back to	Specify a telephone number or an IP address to make the Host disconnect and reconnect to the specified telephone number or IP address, if a Guest connects by a communication profile that uses a point-to-point or network point-to-point communication device. Call back to a specified telephone number or IP address enable connections only from a Guest on a computer with this telephone number or IP address.
Roving call back	Select this option to request a call back telephone number or IP address from a Guest that connects by a communication profile that uses a point-to-point or network point-to-point communication device. When the Host receives this information, it disconnects and reconnects to the specified telephone number or IP address. Roving call back is typically used to make connection costs payable by the Host organization, for example when a traveling employee connects to the home computer.

See also

[Guest Access Security](#) (Guest Access Privileges tab)

5.2.6 Help Providers

In connection with a help request, if help providers are found, but no problem description and/or no Help provider was specified in the **Program Options** dialog box in the **Help Request** tab, the **Help Providers** dialog box is displayed.

Specify a problem description and a help provider:

Option	Description
Problem description	This field displays any problem description specified in the Program Options dialog box in the Help Request tab. You can leave the field empty or specify or edit a problem description.
Help providers	Names of help providers found (on Netop Guest named help services) are displayed in the Help providers pane. Select one and click on Select to deliver the help request to the selected help provider.

5.2.7 Help Request

Select one of these options:

Option	Description
Use the help service to search for help providers	Select this option to request help from a help service.
Use service ticket to connect to a specific help provider	Select this option to request help by a received service ticket number. Selecting this option enables the following fields: <ul style="list-style-type: none"> • Service ticket: In this field, specify the service ticket number. • Problem description: In this field, you can describe your problem.

NOTE: This dialog box displays only the service ticket fields if **Enable Service Tickets** is selected in the **Program Options** dialog box in the **Help Request** tab. A **Netop OnDemand** enabled **Guest** can issue service ticket numbers and forward a service ticket number to you to enable you to return a help request.

See also

[Set up Help Request on Guest and Host Program Options](#) (Help Request tab)

5.2.8 Maintenance Password

You can protect the **Host** setup with a maintenance password, so that no unauthorized people can make changes to the **Host** setup.

Use the Maintenance Password dialog box to specify a maintenance password, what it protects, and Host configuration files (* .**ndb**) protection.

Click on the **Change Maintenance Password** button to display the **Change Maintenance Password** dialog box, where you can specify the maintenance password (max. 64 characters), change it, or disable it by deleting it.

Specify what the maintenance password should apply to and when:

Maintenance password required for

Option	Description
Guest access security	Select this check box to apply maintenance password protection to the Guest Access Security command on the Tools menu and the Guest Access Security button on the toolbar.
All other configuration	Select this check box to apply maintenance password protection to all other setup commands on the Tools menu and other tool buttons on the toolbar.
Unload and Stop	Select this check box to apply maintenance password protection to unloading the Host and stopping the Host . Apply Unload and Stop maintenance password protection to prevent Host stop or unload that make it unavailable for connection and/or to protect security configuration files.
Confirm access	Select this check box to require the user to enter the maintenance password before the remote session can begin. Using Confirm access, the local user on the Host machine has the ability to allow or deny the remote session. In some situations, such as large industrial environments or senior executives within a large organization, the maintenance password is often known by the local Host user. As an extra level of security and to help prevent unauthorized users from allowing the remote support session, the local user on the Host machine can now enter the maintenance password in the Confirm Access Password dialog box before the remote session can begin.

Protect security configuration files

Option	Description
Protect by maintenance password only (if applies)	Protect Host setup only by any applied maintenance password protection. This does not protect Host configuration files (default selection).
Protect files when connected	Protect Host configuration files and disable setup commands on the Tools menu when the Host status is " Connected " to prevent a connected Guest from changing Host setup.
Protect files when connected and running	Protect Host configuration files and disable setup commands on the Tools menu when the Host status is " Connected ", " Help requested " or " Running " to prevent a Host computer user from changing the Host setup. Combined with the Unload and Stop option, the maintenance password protection also prevents the Host user from stopping and unloading the Host and then changing the Host security configuration files.

NOTE: **Host** configuration files (*.ndb) are located in the Netop configuration files folder, typically C:\Documents and Settings\All Users\Application Data\Netop\Netop Remote Control\Host.

If maintenance password protection is enabled, a dialog box prompting you to enter the maintenance password is displayed when you select a protected command or click a protected button. There is no limit to the number of maintenance password attempts.

5.2.9 Program Options

General Tab

Use the **General** tab to specify startup and connection options.

Startup

Option	Description
Start Host when loaded	Select this check box to start the Host and enable communication when loaded.
Load Host at Windows startup (run as service)	Select this check box to load the Host when Windows starts on the computer.

	<p>NOTE: Loading the Host at Windows startup and starting the Host when loaded makes the Host ready for connection when the Host computer is started, even if no user is logged on to Windows.</p>
Minimize Host when loaded	Select this check box to minimize the Host to a Netop Host icon when loaded.
Stealth mode (hide Host when started)	<p>Select this check box to load the Host hidden to the Host computer user. If hidden, nothing on the screen indicates that the Host is loaded.</p> <p>NOTE: To display a hidden Host, execute the showhost.exe file. The showhost.exe file is located in the folder where the Host is installed.</p>

Connection

Option	Description
Minimize Host on connection with Guest	Select this check box to minimize the Host window to a Netop Host icon when a Guest connects.
Host top most window on connection with Guest	Select this check box to display the Host window in front of any other window when a Guest connects.
Show file transfer status	Select this check box to display the File Transfer Status window when a Guest starts a file transfer session.
Send keep alive message	<p>Select this check box to send a data packet at intervals while connected to alert the Host user if the connection is lost.</p> <p>NOTE: To maintain an ISDN (CAPI) connection during short periods of inactivity, do not select this check box. Instead select the Short-hold mode check box in the Edit dialog box for the ISDN (CAPI) communication profile.</p>
Allow Multiple Simultaneous Guest Sessions	Select this check box to allow multiple Guest connections to the Host at the same time.

Host Name tab

Use the **Host Name** tab to specify **Host** naming, name options and the Netop Name Server name space ID.

Naming

This section specifies the name by which the **Host** identifies itself when communicating.

To communicate by a communication profile that uses a networking communication device (NetBIOS, IPX, TCP/IP, Terminal Server), it is necessary that each **Host** use a unique name. A **Host** that uses a name that is already used by another communicating **Host** is denied communication.

Select one of these options:

Option	Description
Enter name or leave name field blank	Select this option to display a field below. Specify a name in the field or leave the field blank to name the Host by the specified name or leave it without a name.
Use environment variable	<p>Select this option to display a field below. Specify an environment variable name in the field to name the Host by the value of the specified environment variable.</p> <p>NOTE: Do not name a network computer Host by the environment variable <code>USERNAME</code> if it is set up to load at Windows startup. If you do that, the Host loads before a user logs on to Windows to get the name <code>%USERNAME%</code> and retains this name until reloaded while a user is logged on to get the name <code><Windows logon user name></code>. Of multiple Hosts named <code>%USERNAME%</code>, only one can communicate.</p> <p>Name a terminal server session Host typically by the environment variable <code>USERNAME</code>. See the Administrator's Guide, Netop Naming (TSE). To display available Windows environment variables, in a command prompt window type set and press ENTER.</p>
Use Windows computer name	<p>Name the Host by the Host computer Windows name.</p> <p>NOTE: Name a network computer Host typically by the Windows computer name. Do not name a terminal server session Host by the Windows computer name. Terminal server session Hosts share the Windows computer name of the terminal server computer. Of multiple Hosts named by the terminal server computer name, only one can communicate.</p> <p>Select the Prefix with computer workgroup name check box to add a prefix to the Host computer name to ensure Host name uniqueness across multiple domains and workgroups. The prefix can be its domain or workgroup name.</p> <p>Use the Separate with field to specify the separator character. The</p>

	default character is a back slash (\), but you can replace it by any other character.
Name	The Host name according to the selection above.

Name options

Option	Description
Public Host name	Select this check box to respond to Guests that browse for Hosts by the Host name. NOTE: If the Host computer is connected directly to a public network like the Internet, you may want to clear the selection of this check box to not invite hacking attempts.
Enable user name	Select this check box to enable the name of a user logged on to the Host computer to enable connections by the user name. NOTE: If this check box is selected, the user name appears on the Names tab of the Host window. You may want to clear the selection of this check box on a server Host to disable connecting by the name of a temporarily logged on user or the user as which the Host runs to acquire the computer rights of the user.

Netop Name Server

In the **Name Space ID** field specify the name space ID specified on Guests with which the Host should be able to communicate by using Netop Name Server. The default name space ID is PUBLIC.

The name space ID applies only if the Host communicates through a communication profile that uses the TCP/IP communication device and for which the Use **Netop Name Server** check box in the **Advanced TCP/IP Configuration** window is selected and Netop Name Servers are specified.

NOTE: For the changes to the naming or name space ID to take effect, make sure to restart the **Host**.

Connection Notification tab

Use the **Connection Notification** tab to specify options for connection notification upon, during and after connection.

Upon connection

Option	Description
--------	-------------

Play sound	Select this check box to play a sound when a Guest connects. The sound file <code>StartHRC.wav</code> is located in the Media folder of the folder in which the Host is installed.
Display Connection List	Select this check box to display the Connection List window when a Guest connects. Specify in the field to the right the number of seconds that this window should be displayed. Default is 6. The value 0 makes the Connection List window remain on the screen.
Password to close Connection List	Select this check box and specify a password in the field below to make the Connection List window remain on the screen until closed manually. Characters are displayed as dots or asterisks. To close the Connection List window, you are prompted to enter the specified password.
Display balloon tip	Select this check box to display a balloon tip from the Netop Host icon when a Guest connects.

During connection

Option	Description
Play sound	Select this check box to play a sound during Guest connection at this interval. In the Interval field specify a number in the range for the interval between sounds in seconds. The sound file <code>ContHRC.wav</code> is located in the Media folder of the folder in which the Host is installed.
Display Guest name (if available) in the title bar	Select this check box to display the connected keyboard and mouse control Guest name in the title bar, the Windows taskbar Netop Host icon and the Netop Host icon tool tip.
Animate icon	Select this check box to animate the Netop Host icon double corner lines during Guest connection.

After connection

Option	Description
Display History List	Select this check box to display the History List window when a Guest disconnects.

	Specify in the field to right the number of seconds this window should be shown. Default is 0. The value 0 makes the History List window remain on the screen.
Password to close History List	Select this check box and specify a password in the field below to make the History List window remain on the screen until closed manually. Characters are shown as dots or asterisks. To close the History List window, enter the specified password.
Display balloon tip	Select this check box to display a balloon tip from the Netop Host icon when a Guest disconnects.

Audio-Video Chat tab

Use the **Audio-Video Chat** tab to specify audio and video settings.

Audio Chat

General

Select the **Enable full-duplex audio** check box to enable sending audio data between **Guest** and **Host** in both directions at the same time.

NOTE: Some computer audio systems do not support full-duplex audio.

Microphone sensitivity

Option	Description
Silence level	Drag the slider bar to specify the microphone sound input level below which no sound data should be transferred.
Line hold	Drag the slider bar to specify the time period in which sound data should continue to be transferred after the microphone sound input level has dropped below the silence level. TIP: Try out different Silence level and Line hold settings to optimize sound transfer.

Click on the **Check sound system** button to test the computer sound system.

Click on the **Advanced** button to display the **Advanced audio settings** dialog box.

See [Advanced audio settings](#).

Video Chat

Click on the **Advanced** button to display the **Advanced Video** dialog box.

See [Advanced Video](#).

Remote Printing tab

Use the **Remote Printing** tab to specify remote Netop printers.

Click on the **Add Printer** button to add a remote printer. Follow the guidelines in the displayed **Add printer guidelines** dialog box. Click on the **Ready** button to start adding a remote Netop printer.

The remote printers that you add, are displayed in the Remote Netop printers pane.

You can remove a Netop printer by selecting it in the pane and clicking on the **Remove Printer** button.

To send a **Host** computer print job to a **Guest** printing device while the **Guest** is connected, print to a **Host** computer remote Netop printer that specifies the **Guest** printing device.

NOTE: Special instructions for remote printing from DOS applications are available in the [Netop KnowledgeBase](#).

See also

[Send a print job to a remote printer](#)

Help Request tab

Use the **Help Request** tab to specify general help request options. If unspecified, the **Host** user can specify individual options with each help request.

Optional help information

Option	Description
Problem description	To always specify the same problem description, specify it in this field. If the field is left empty, the Help Providers window is displayed when requesting help, allowing you to specify a problem description for the individual help request.
Help provider	To always request help from the same help provider (help service), specify its name in this field.

	If the field is left empty, the Help Providers window is shown when you request help, allowing you to specify a help provider for the individual help request.
--	---

Communication

Communication profile

Option	Description
Use current Host communication profiles	Select this option to send help requests by enabled communication profiles. Unless only one communication profile or only communication profiles that use networking communication devices are enabled, the Select Help Request Communication Profile dialog box is displayed when requesting help.
Use specific Communication Profile	Select this option and select one of the available Host communication profiles in the drop-down list to use a specific communication profile.

Click on the **Advanced** button to display the **Advanced Help Request Options** dialog box. See [Advanced Help Request Options](#).

Options

Option	Description
Add Help Request icon to the tray	Select this check box to add a help request icon (a life belt) to the notification area in the lower right corner of the screen. If this icon is added, the Host computer user can request help even if the Host is hidden. To request help, double-click on the icon or right-click on the icon and select Request Help .
Enable Help Service	Select this check box to enable help request by a help service.
Enable Service Tickets	Select this check box to enable help request by a service ticket.

[See also](#)

[Request help](#)
[Set up Help Request on Guest and Host](#)

Run As tab

Use the **Run As** tab to enable running the Host with the rights of a Windows user account if no user is logged on to the Host computer, the **Host** runs with extensive **Host** computer rights but no network computer rights. See the [Administrator's Guide](#), Netop Remote Control Processes and Windows Security. If a user is logged on to the **Host** computer, the **Host** runs with the rights of the logged on user.

Run Host as specific user

Option	Description
Enable	Select this check box to always run the Host as a specific Windows user account.
User name	Specify the Windows user account name.
Password	Specify the corresponding password.
Domain	Specify the corresponding domain. CAUTION! Consider carefully in each case the benefits and drawbacks including security risks of always running the Host as a specific Windows user account. In some cases, you should run the Host as a Windows user account created exclusively for this purpose.
Automatically change to random password every week	Select this check box to change the password of the credentials specified above immediately and every week into a random password to automatically satisfy a password change policy. CAUTION! Do not select this check box if the credentials specified above belong to a user person, as the user person cannot know the random password.

Directory Services tab

Use the **Directory Services** tab to specify directory services to enable authenticating connecting **Guests**.

Click on the **Add** button to add a directory service. The **Directory Service** dialog box in which you can specify the directory service that you want to use is displayed. See [Directory Service](#).

The name of the directory service and the directory server IP address or DNS name is displayed

in the pane on the **Directory Services** tab.

To edit the properties of the directory service record, select the record in the pane and click on the **Edit** button.

To remove the directory service, select the record in the pane and click on the **Delete** button.

See also

[Guest Access Security](#) (Grant Each Guest Individual Access Privileges Using Directory Services tab).

Multi-Factor Services tab

Use the **Multi-Factor Services** tab to enable multi-factor authentication when connecting **Guests**.

Click on the **Add** button to add the corresponding Multi-Factor service. The **Multi-Factor Service** dialog box in which you can specify the multi-factor service that you want to use is displayed.

Multi-Factor Service Settings

Option	Description
Name	Specify a name for the multi-factor service to be defined.
Multi-Factor Service Type	The list of services which help safeguard access to data and applications. Netop Remote Control currently provides integration to Windows Azure Multi-Factor Authentication.
Client Certificate	Click on the Choose certificate... button and browse for the Windows Azure certificate to be used for the Windows Azure Multi-Factor Authentication.
LDAP Phone No Attribute	The LDAP attribute identifying the user's telephone number. It will be used to send user the token to be used for multi-factor authentication.
Apply to all roles	Select this check box to apply the current multi-factor authentication service to all roles defined in the Directory Services. NOTE: Multi-factor authentication applies to all roles only if the Guest Access Method selected from Tools > Guest Access Security is either Grant each Guest individual access privileges using Windows Security Management or Grant each Guest individual access privileges using Directory services.

To edit the properties of the Multi-Factor service record, select the record in the pane and click on the **Edit** button.

To remove the multi-factor service, select the record in the pane and click on the Delete button. In case there are multiple roles which can apply for a specific authenticating user, each potentially with a different multi-factor authentication services, the multi-factor authentication service to be chosen is the one with the highest priority from the list. Order in the list dictates the priority, top items having the highest priority.

See also

[Guest Access Security](#) (Grant Each Guest Individual Access Privileges Using Directory Services tab).

Web Update tab

Use the **Web Update** tab to specify web update options to automatically update the **Host** installation.

Web Update Settings

Option	Description
Update server	Specify the web address of the server from which to download Host update files (default: update.netop.com, the Netop manufacturer web update server). NOTE: To update the Netop installations in an organization, we recommend publishing new updates to an internal web update server (select Publish New Updates on the Tools menu).
HTTP Proxy	Specifying a HTTP proxy is typically not required. Before specifying a HTTP proxy, click on the Update now button to test the web update connection. If you receive a message indicating connection to the update server, specify no HTTP proxy. If Update now yields no connection, click on the Detect button to make Netop attempt to detect the HTTP proxy server and display its name and port number in the HTTP Proxy field. Click on the Update now button to test the connection. If unsuccessful, consult your network/system administrator about what to specify in the HTTP Proxy field (format: <Server name>:<Port number>).
Update now	Click on this button to connect to the update server specified in the Update server field. A web update message notifies you if the connection to the update server fails, if no updates are available or if updates are available, and in the latter case ask you if you want to download and install updates.
Schedule	Click on this button to display the Web Update Schedule dialog box and specify

	a schedule of checks for updates including download and installation of available update files.
--	---

5.2.10 Select Directory Services Users or Groups

The **Select Directory Services Users** dialog box and the **Select Directory Services Groups** dialog box are similar.

The directory services users or groups that you add here are added to the security role selected in the **Guest Access Security** dialog box on the **Guest Access Privileges** tab.

The upper pane displays directory services specified in the **Program Options** dialog box on the **Directory Services** tab.

Users or groups are displayed below the individual directory services in the pane.

Select a user or group in the upper pane and click the **Add** button. The user or group is added to the lower pane. They are displayed by their distinguished name, for example the directory path and common name of the user/group, and the directory service name as specified in the **Program Options** dialog box on the **Directory Services** tab.

See also

[Guest Access Security](#) (Guest Access Privileges tab)
[Directory Service](#)

Index

- A -

Active Management Technology (AMT) 33, 34, 36
 Add to Phonebook 10
 adding a remote printer 60
 adding phonebook references 14
 adding sections 28
 Advanced audio settings dialog box 65
 Advanced Help Request Options dialog box 133
 Advanced Help Service dialog box 65
 Advanced inventory option dialog box 67
 Advanced TCP/IP Configuration dialog box 68
 Advanced Video dialog box
 compression 69
 driver 69
 alerts 36
 Allowed Network Numbers dialog box 133
 AMT (Active Management Technology) 33, 34, 36
 AMT, vPro 33, 34, 36
 audio 65
 audio-video chat 50, 58, 151
 authentication
 Digest 34
 Kerberos 34

- B -

bindings 68
 BIOS 33, 36
 Blank Display 15
 booting 33, 36

- C -

cache 80
 call back 136, 147
 capturing video 62
 certificate 34
 chat 50, 58, 151
 clickable bitmap 47
 clipboard 57
 cloning files 42, 108
 Command Console 25
 command prompt 25
 communicating with Guest user 50

communicating with Host user 58
 communication 80
 communication devices 70, 78
 Communication Profile Edit dialog box 70
 Communication Profile Setup dialog box 78
 communication profiles 52, 70, 78
 Compression/Encryption 80
 Connect 80
 connect problems 91
 Connect to Host dialog box 79
 Connect using
 communication profile 79
 local 79
 phonebook file 79
 connecting 49
 connection 151
 Connection Properties dialog box
 Compression/Encryption tab 80
 Connect tab 80
 Custom tab 80
 Desktop tab 80
 Display tab 80
 Keyboard/Mouse tab 80
 Logon tab 80
 Protect Item tab 80
 Record tab 80
 Startup tab 80
 copying 30
 copying files 42
 credentials 34, 147
 Custom 80
 custom inventory items 16, 67
 Custom Inventory Items dialog box 91
 customizing commands 36
 cycling power off and on 36

- D -

demonstrating 61
 Desktop 80
 Directory Service dialog box 134
 directory services 136, 151, 162
 Disconnect, Host 51
 disconnecting 49
 Disk Drives 20
 Display 80

- E -

editing communication profiles 70

editing phonebook records 11
 Encryption 113, 136
 ending a session, Host 51
 error handling 92
 Event Management tab 36
 Event Properties 21
 Event Viewer 21
 Execute Command 18
 executing system control commands 18
 exporting phonebook data 12

- F -

File Manager 42
 File Manager Options dialog box 108
 file transfer 30, 42
 confirming deletion/overwriting 108
 filters 36

- G -

Gateway 70
 generating inventory 15
 Get Inventory 15
 Global Settings dialog box 92
 groups 136
 Guest Access Privileges 136
 Guest Access Security 147
 Guest Access Security dialog box 136
 Guest ID 147
 Guest Policy 136
 Guest Profile dialog box 147

- H -

help provider 49, 52, 133, 149
 Help Providers dialog box 149
 help request 49, 55, 149, 151
 executing actions 65
 Gateway logon credentials 133
 IP address 133
 notification 65
 phone number 133
 Remote Control 113
 Remote Control OnDemand 113
 running a local program 65
 sending a message 65
 setting up 52
 Help Request dialog box 149
 Help Request setup

Guest 52
 Host 52
 Help Request tab 55
 help service 49, 52, 113, 149, 151
 Host inventory 15
 Host name 151
 Host name qualifier 70
 Host PC information 80

- I -

IDE redirection 36
 importing phonebook data 12
 incoming help requests 55
 integrating applications 28
 Intel Active Management Technology 33
 Intel Setup and Configuration Service 33
 Intel vPro 33, 113
 Intel vPro Event Log 36
 Intel vPro tab 34
 interface 68
 inventory 15, 25, 91, 113
 Inventory dialog box 90
 Inventory tab 15, 16
 IP address 68
 IP broadcast list
 DNS name 94
 IP address 94
 IP Broadcast List dialog box 94
 IPX communication 113
 ISDN communication 133

- K -

keyboard and mouse control 15
 Keyboard/Mouse 80
 keystrokes, sending 56

- L -

Local Users and Groups 26
 Lock Keyboard and Mouse 15
 Lock Workstation 18
 log file 92
 Log Off 18
 Log Properties 21
 Log Setup dialog box (Host) 95
 logging
 file transfer 108
 logging events

logging events
 Log Locally 44
 Log on Netop Server 44
 Log to Windows Event Log 44
 Log using SNMP Traps 44
 logging events (Host)
 locally 95
 on Netop server 95
 to Windows event log 95
 using SNMP traps 95
 Logon 80

- M -

MAC/IP Address List Setup 136
 magnifying on Host screen 64
 Maintenance Password dialog box 150
 managing
 alerts 36
 filters 36
 subscriptions 36
 Marker Mode 64
 marking objects on Host screen 64
 masking windows 61
 message 58
 Microsoft Management Console (MMC) 19
 MMC (Microsoft Management Console) 19
 Modem Configuration dialog box 112
 Modem dialog box 112
 monitoring Hosts 17
 moving files 42
 multi chat session 58
 multi Guest session 55
 multimedia devices 65

- N -

Name Not Found dialog box 91
 name space ID 151
 naming 151
 Netop authentication 136
 Netop log
 event codes and arguments (Guest) 100
 event codes and arguments (Host) 102
 Netop Marker Utility 64
 Netop Name Server 68, 151
 Netop OnDemand
 Help Request 149
 Netop Screen Video 62
 Netop Security Server 136

Netop Skin Designer 47
 Netop Tunnel 39
 notification 151
 animated Host icon 49
 balloon tip 49
 connection list 49
 history list 49
 Host title bar 49
 Novell Network Numbers dialog box 113

- O -

Options
 File Manager 108
 organizing 12
 overwrite/delete 92

- P -

password 147
 phonebook 11, 14
 creating records in 10
 exporting data 12
 folders 12
 History tab 10
 importing data 12
 Quick Connect tab 10
 Remote Desktop access 14
 save connection information to 10
 phonebook records
 password protection 11
 Phonebook tab 10, 14
 playback device 65
 playing back session recordings 46
 port numbers 68
 powering off, on 36
 processing inventory information 16
 Program Options dialog box, Guest
 Audio-Video Chat tab 113
 Cache tab 113
 Clipboard tab 113
 Directory Services tab 113
 Encryption tab 113
 General tab 113
 Help Request tab 113
 Host Name tab 113
 Intel vPro tab 113
 Inventory tab 113
 Layout tab 113
 Logon tab 113
 Monitor tab 113

Program Options dialog box, Guest
 Recording tab 113
 Remote Control tab 113
 Remote Printing tab 113
 Run tab 113
 Skins tab 113
 Smart Card tab 113
 Sounds tab 113
 Web Update tab 113
 Program Options dialog box, Host
 Audio-Video Chat tab 151
 Connection Notification tab 151
 Directory Services tab 151
 General tab 151
 Help Request tab 151
 Host Name tab 151
 Multi-Factor Services tab 151
 Remote Printing tab 151
 Run As tab 151
 Web Update tab 151
 Protect Item 80
 protecting phonebook record files 11
 protecting setup with a password 150
 provider 149
 provisioning 33
 public key 136

- R -

RDP 14
 rebooting 36
 Record 80
 Record Session 45, 46
 recording device 65
 redirecting a print job 60
 redirecting print jobs 61
 redirection 33
 Registry
 Keys pane 22
 Values pane 22
 Remote Control OnDemand 52
 Remote Desktop access
 phonebook 14
 Remote Desktop Entry 14
 Remote Management 19
 Disk Drives 20
 Event Viewer 21
 Registry 22
 Services 22
 Task Manager 22
 Windows Event Log 21

Remote Management pane 20
 remote printing 60, 61
 requesting help 49
 responding to a help request 55
 Restart 18
 Retrieve from Host 57
 Run dialog box 129
 Run Program 41
 running a program 113
 running a program after inventory scan 67
 running a program on a Host 41
 running a remote program 129
 running a script
 File Manager 42
 running Host as specific user 151

- S -

Save Screen to Clipboard 57
 Save Screen to File 57
 script 92
 commands 130
 creating 30
 global settings 130
 Script command
 Inventory 90
 Send Message 132
 script commands 30
 Script dialog box 130
 SCS 33
 Secure Tunnel 39
 security roles 136
 Select Directory Services Users or Groups dialog box 162
 Send Alt+Print Screen 56
 Send Alt+Shift+Tab 56
 Send Alt+Tab 56
 Send Clipboard 57
 Send Ctrl+Alt+Del 56
 Send Ctrl+Esc 56
 Send Message dialog box 132
 Send Print Screen 56
 sending a print job to a remote printer 60
 sending keystrokes 56
 sensors 36
 service tickets 52, 55, 149, 151
 Services 22
 session recordings 45, 46
 Sessions 30
 Shared Folders

Shared Folders
 Shares tab 24
 special shares 24
Shares tab 24
sharing your screen 61
Shut Down 18
Skin Repository Server 47
skins 47, 80, 113
Smart Card 113, 136
special shares 24
startup 80, 151
subscriptions 36
support 149
synchronizing 108
synchronizing files 42
System Control
 actions to perform 25
 current host state 25
 displaying a message on the Host computer 25
 options 25

- T -

Task Manager 22
TCP/IP
 UDP 70
TCP/IP (TCP IPv6) 70
TCP/IP (TCP) 70
TCP/IP, advanced options 68
Terminal Server 70
tickets 52, 55, 113
TLS (Transport Layer Security) 34
transfer 92
transfer clipboard 57
transferring files 42
Transport Layer Security (TLS) 34
Tunnel 39

- U -

user name 151
users 136
using skins 47

- V -

video 62
vPro
 add to phonebook 34
vPro Console 33, 36

logging on 34
vPro, AMT 33, 34, 36

- W -

Wake on LAN 18
web update 113, 151
WebConnect 70
WebConnect tickets 52, 55, 113
Windows computer name 151
Windows event log 21
Windows Security Management 136
writing on Host screen 64
